



Imaging Engine - FlexRip 14

Approval

© Copyright 2014 Esko Software BVBA, Gent, Belgium

All rights reserved. This material, information and instructions for use contained herein are the property of Esko Software BVBA. The material, information and instructions are provided on an AS IS basis without warranty of any kind. There are no warranties granted or extended by this document. Furthermore Esko Software BVBA does not warrant, guarantee or make any representations regarding the use, or the results of the use of the software or the information contained herein. Esko Software BVBA shall not be liable for any direct, indirect, consequential or incidental damages arising out of the use or inability to use the software or the information contained herein.

The information contained herein is subject to change without notice. Revisions may be issued from time to time to advise of such changes and/or additions.

No part of this document may be reproduced, stored in a database or retrieval system, or published, in any form or in any way, electronically, mechanically, by print, photo print, microfilm or any other means without prior written permission from Esko Software BVBA.

This document supersedes all previous dated versions.

PANTONE®, PantoneLIVE and other Pantone trademarks are the property of Pantone LLC. All other trademarks or registered trademarks are the property of their respective owners. Pantone is a wholly owned subsidiary of X-Rite, Incorporated. © Pantone LLC, 2012. All rights reserved.

This software is based in part on the work of the Independent JPEG Group.

Portions of this software are copyright © 1996-2002 The FreeType Project (www.freetype.org). All rights reserved.

Portions of this software are copyright 2006 Feeling Software, copyright 2005-2006 Autodesk Media Entertainment.

Portions of this software are copyright ©1998-2003 Daniel Veillard. All rights reserved.

Portions of this software are copyright ©1999-2006 The Botan Project. All rights reserved.

Part of the software embedded in this product is gSOAP software. Portions created by gSOAP are Copyright ©2001-2004 Robert A. van Engelen, Genivia inc. All rights reserved.

Portions of this software are copyright ©1998-2008 The OpenSSL Project and ©1995-1998 Eric Young (eay@cryptsoft.com). All rights reserved.

This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>).

Adobe, the Adobe logo, Acrobat, the Acrobat logo, Adobe Creative Suite, Illustrator, InDesign, PDF, Photoshop, PostScript, XMP and the Powered by XMP logo are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States and/or other countries.

Microsoft and the Microsoft logo are registered trademarks of Microsoft Corporation in the United States and other countries.

SolidWorks is a registered trademark of SolidWorks Corporation.

Portions of this software are owned by Spatial Corp. 1986 2003. All Rights Reserved.

JDF and the JDF logo are trademarks of the CIP4 Organisation. Copyright 2001 The International Cooperation for the Integration of Processes in Prepress, Press and Postpress (CIP4). All rights reserved.

The Esko software contains the RSA Data Security, Inc. MD5 Message-Digest Algorithm.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Sun Microsystems in the U.S. and other countries.

Part of this software uses technology by BestTM Color Technology (EFI). EFI and Bestcolor are registered trademarks of Electronics For Imaging GmbH in the U.S. Patent and Trademark Office.

Contains PowerNest library Copyrighted and Licensed by Alma, 2005 – 2007.

All other product names are trademarks or registered trademarks of their respective owners.

Correspondence regarding this publication should be forwarded to:

Esko Software BVBA

Kortrijksesteenweg 1095

B – 9051 Gent

info.eur@esko.com

Table of Contents

Table of Contents	4
1 Preface	8
1.1 Who is this guide aimed at?	8
1.2 What does this Manual contain?	8
1.3 Conventions	8
1.3.1 Layout	8
2 General introduction	10
3 Introduction to a FlexRip workflow	11
3.1 What is a FlexRip?	11
3.2 What kind of FlexRip flavors exist?	11
3.3 What is a FlexRip/Approval?	12
3.4 FlexRip basics	13
3.4.1 General PS and Esko native workflow	13
3.4.1.1 PostScript workflow	14
3.4.1.2 Native workflow	14
3.4.2 Which file formats can be sent?	15
3.4.3 Workflow description	16
3.5 What is a FlexRip Queue?	18
4 Startup and shutdown of FlexRip	19
4.1 Why and when?	19
4.2 How to start up a FlexRip?	19
4.2.1 Start up the computer	19
4.2.2 Starting up the Rip	20
4.3 How to shut down a FlexRip?	20
4.3.1 Stopping the Rip	20
4.3.2 Shutting down the computer	21
4.4 How to reboot the FlexRip computer?	21
5 An overview of programs on the Esko FlexRip	22
5.1 General	22
5.2 Which logon to use?	23
6 Dispatcher	24
6.1 General	24
6.2 Rip menu	25
6.2.1 Clear History	25
6.2.2 Send Jobs	25
6.2.3 Abort Job	26
6.2.4 Restart PS RIP.....	27
6.2.5 Exit	27
6.3 Options menu	27
6.3.1 Program options	27
6.3.1.1 FlexRip Log Files	28
6.3.1.2 Automation Engine Server Disk Mounting	28
6.3.1.3 Trace messages and History	28

6.3.1.4 Input Queue Settings	29
6.3.1.5 Advanced	29
6.3.2 Queue defaults	29
6.3.3 Performance	30
6.3.4 Rip priority	30
6.4 Tools menu.....	31
6.4.1 History View	31
6.4.2 Status Monitor	31
6.5 Info menu	31
6.5.1 Ports	32
6.5.2 About Dispatcher	32
6.6 Connected monitors	32
6.7 Input queues	32
6.7.1 Possible queue types	32
6.7.2 New - Queue Info - Delete	33
6.7.2.1 General	37
6.7.2.2 File handling	38
7 Queue Settings	42
7.1 Priority of settings	42
7.2 Basic	43
7.2.1 Device type	44
7.2.2 Device name	44
7.2.3 Resolution	44
7.2.4 Rotation	44
7.2.5 Page size	44
7.2.5.1 Oversized image.....	45
7.2.6 OFE details	45
7.2.7 Imaging options.....	45
7.2.7.1 Dot Shape.....	45
7.2.7.2 Laydown order.....	47
7.2.7.3 Laydown options.....	47
7.2.7.4 Mirror.....	49
7.3 Output	50
7.3.1 Location & Name	50
7.3.1.1 Output location	50
7.3.1.2 Output file name	51
7.3.1.3 Restricted file names	51
7.3.1.4 Delete temporary LP files.....	51
7.3.2 Configuration set	51
7.3.2.1 Name	52
7.3.2.2 Media saving.....	52
7.4 PS/PDF Input	54
7.4.1 PostScript	55
7.4.1.1 Screen type	55
7.4.1.2 Screen Swap Table	57
7.4.1.3 Pure black overprint	57
7.4.1.4 Enable optimization	57

7.4.1.5	Preserve Quark trapping	58
7.4.1.6	Ignore PS color management	58
7.4.2	PDF	58
7.4.2.1	PDF password	58
7.4.2.2	Ignore calibrated colorspaces	59
7.4.3	Images	59
7.4.3.1	Abort for images with scaled resolution below ... dpi	59
7.5	Native Input	59
7.5.1	Screening	60
7.5.2	Abort for images with scaled resolution below... dpi	61
7.6	Curve Pilot	61
7.6.1	Press dot gain compensation	63
7.6.2	Calibration	63
7.7	PS/PDF marks	63
7.7.1	Layout mode	64
7.7.2	Include	65
7.7.2.1	Color strip	65
7.7.2.2	Customer logo	65
7.7.2.3	Data legend	66
7.8	Screening	66
7.9	Advanced options.....	69
7.9.1	Color conversion.....	69
7.9.2	Use & Color management.....	69
7.9.3	Optimize separated postscript file processing.....	69
7.9.4	External search paths.....	70
7.10	Debugging	71
7.11	Copydot Tuning	72
7.11.1	Background	72
7.11.1.1	Performance & Memory Management	72
7.11.1.2	Copydot workflow	72
7.11.1.3	Copydot and paint modes	73
7.11.2	Queue Settings	73
7.11.2.1	Resample	76
7.11.2.2	Abort	76
8	Status Monitor	77
8.1	General overview	77
8.2	Server menu	78
8.2.1	Connect to	78
8.2.2	Trace messages	79
9	History View	80
9.1	Log files: guidelines	83
10	Workflow: flavors and hints	85
10.1	Who decides: the FlexRip or the operator?	85
10.2	What is best: AppleTalk or Hot Folders?	85
10.3	What if you rip for more than one output device?	85
11	Screening on FlexRip	86

12 Curve Pilot: Esko's Dot Gain Compensation tool	87
12.1 Terminology	87
12.2 Basic explanation and general workflow	87
12.3 Where are my SCR(DGC) files and Strategies?	88
12.4 Using old DGC files	89
13 Data backup and customization	90
14 Classic errors and their explanation	91
14.1 Classic PostScript errors	92
14.1.1 Examples	92
14.1.2 Problem solving: 'capture' the PS file	94
14.2 Classic internal errors	94
15 General troubleshooting	97
15.1 Queue settings 'disappear'	97
15.2 My input queue shows a 'fail' status	97
15.3 The system disk is filling up	98
15.4 FlexRip rips my file over and over again	98
16 Frequently Asked Questions.....	100
16.1 FlexRip software version	100
16.2 Extra software on the FlexRip	100
16.3 Screensaver	100
16.4 Windows version	100
16.5 Rebooting the FlexRip	101
16.6 FlexRip's computer name	101
16.7 Info on the network address	101
17 Appendix	103
17.1 Connection to DTP stations	103
17.1.1 How to share FlexRip volumes for a Macintosh (Microsoft Windows 2000 or 2003 Server)	103
17.1.2 How to share FlexRip volumes for a PC (Microsoft Windows 2000 Server)	110
17.1.3 How to share FlexRip volumes for a Macintosh or a PC (Microsoft Windows 2000)	111
17.1.4 How to mount FlexRip volumes on a PC (Microsoft Windows 2000) ..	112
17.1.5 How to mount FlexRip volumes on a Macintosh OS9 or older.....	113
17.1.6 How to mount FlexRip volumes on a Macintosh OSX or later	113
17.2 Merging	113
17.3 What about OPI?	113
18 Glossary	115
INDEX	119

1 Preface

1.1 Who is this guide aimed at?

This manual introduces you to the FlexRip application. You will find all the necessary information you need to make you feel at ease working with FlexRip. It is meant to be equally helpful to first time users and skilled operators who might need a little extra assistance from time to time.

1.2 What does this Manual contain?

This FlexRip manual basically consists of the following parts:

- Introduction to a FlexRip/Approval workflow
- Startup and shutdown of a FlexRip
- General overview of programs on the FlexRip
- Dispatcher
- Queue Settings
- Status Monitor
- History View
- Workflow: flavors and hints
- Screening on FlexRip
- Esko Curve Pilot: Esko's Dot Gain Compensation tool
- Data backup and customization
- Classic errors and their explanation
- General troubleshooting
- Frequently Asked Questions
- Appendix

1.3 Conventions

1.3.1 Layout

For easy reference, we use the following conventions:

Each topic of a list will be preceded by a bullet.

Instructions of only one step, or instructions independent of the order of the steps, are also preceded by a bullet.

1. For instructions that consist of several steps to be performed in a strict order, we use numbered steps.

Note

A note gives you important information.

Tip

A tip gives you useful information.

Warning

A warning gives you information on how to avoid problems.

Task

indicates a reference to a task.

If a task is referred to in the See also-sections it is preceded by the words “How to...”

2 General introduction

This document is the user and training manual of a FlexRip/Approval and is intended for all operators. It explains a FlexRip workflow, the setup of possible configurations, describes its daily use and contains some basic troubleshooting. This document is currently available as PDF file or on-line help. A FlexRip comes with the Suite 12 DVD that contains the following:

1. Software
2. User documentation on:
 - FlexRip/Approval (this document) (PDF file: Acrobat)
 - Curve Pilot
 - Esko Screening
 - SambaFlex Screens

Warning

This document (and a FlexRip training in general) assumes that the operators of a FlexRip are at least comfortable with the basics of the Windows operating system. A daily user of FlexRip does not need detailed knowledge, but the system manager who controls the in-house networking, installation and configuration of Windows does. This implies that he should have no problems reading our installation and update documentation, written in English. If this is not the case, Esko strongly advises the customer to have his system manager follow a Windows training program.


3 Introduction to a FlexRip workflow

3.1 What is a FlexRip?

1. A FlexRip is designed as a file RIP. There is no direct interfacing with non-Esko machines to ensure maximum connectivity, flexibility and performance.
2. FlexRip is a true Dual Channel RIP. It is equipped with an Esko native channel and an Adobe Certified PS/PDF channel to guarantee a fully open platform.
3. The FlexRip engine is Esko technology and a continuation of the FastRip technology. FlexRip has the same engine for all flavors.
4. FlexRip contains various output modules for different output device types (proofers, ImageSetters, PlateSetters), but only 1 kernel to guarantee a 100% consistency.
5. FlexRip comes standard with Esko Curve Pilot, the advanced calibration tool for film output, plate calibration and press compensation.
6. FlexRip is based on a very modular design, so different output flavors can be added at any time.

3.2 What kind of FlexRip flavors exist?

FlexRip is a modular product with different input channels and a variety of output flavors.



1. Input channels:

- PostScript 3 / PDF 1.4 / PDF 1.5 / PDF 1.6
- Normalized PDF and GRO (Esko's native file formats)

Note

FlexRip 12 is compatible with Automation Engine 12, PackEdge 12 and Plato 12 for PS/PDF interpretation.

2. Output flavors:

- FlexRip/Approval provides an interface with Kodak's Approval proofer machines.
- FlexRip/B either rips on the fly (Esko native only) or rips to (screened bitmap) files before sending the information to the Barco ImageSetter (PS and Esko native).
- FlexRip/C outputs screened LEN files for CDI's.
- FlexRip/DCS screened output is a generic module to generate DCS 2.0 files.
- FlexRip/DCS unscreened output provides generic unscreened DCS 2.0 files.
- FlexRip/P outputs (un)screened PDF or PostScript files.
- FlexRip/Proof outputs to proofing devices. Various output formats are available: TIFF, PS, RTL, PDF, Windows Printer, and E Printer.
- FlexRip/TG (TIFF/Gray) outputs grayscale (8-bit) TIFFs (unscreened).
- FlexRip/T4 outputs screened bitmap TIFF files (1-bit).

3.3 What is a FlexRip/Approval?

FlexRip/Approval is a dedicated interface for all workflows going to Kodak's Approval proofer machines. It outputs screened files and communicates directly to the Kodak software which outputs them on the machine. In order to optimize the performance and communication between the RIP and the output device, this flavor is best installed on the controller PC of the Kodak Approval itself. However, it can also be installed on other FlexRips but in this case heavy network traffic will take place. This may affect the performance. If FlexRip/Approval is installed on the same pc as the Kodak OFE host software, no other FlexRip flavors are allowed on the same PC, this to avoid interference with the controller software and performance hits.

FlexRip/Approval fully supports Kodak's Recipe colors.


Advantages over PostScript RIPs:

- The overall speed, accuracy and repeatability.
- The complete range of Esko screens is available.
- Esko's Esko Curve Pilot: Dot Gain Compensation tools.
- Esko's flexo distortion.
- Esko's optimized imaging quality.
- Combines Esko's Screen in Screen technology with Kodak's Recipe color technology to simulate special colors in order to save on consumable cost.
- Advanced support for opaque colors.

3.4 FlexRip basics

3.4.1 General PS and Esko native workflow

This is a general presentation of a FlexRip workflow:



3.4.1.1 PostScript workflow

In a PostScript workflow, the DTP operator (Macintosh or PC) will print an output-ready job via the Print menu in the application. Using the printer driver of Adobe PS and Esko's dedicated output device PPDs, the operator sets following job parameters in the (separated) PostScript file:

- the selection of separations to be printed
- screening parameters: dot, screen ruling (lines per inch or lpi), angle
- job size
- DGC, Strategy (*.icpro) or CurveSet (*.prsync) Esko's compensation curves. See the Curve Pilot chapter (page 87) for a short introduction and the dedicated Curve Pilot documentation on the Suite 12 DVD for an in-depth explanation.)
- positive or negative; right or wrong reading
- distortion (flexo-printing issue)

Some settings may be left out as they can be set default in a specific RIP queue (e.g. expose resolution, output folder,...). The PostScript file ends up (via AppleTalk print queue, Hot Folder,...) on the FlexRip and is ripped automatically, using default or job-specific RIP options.

The output files will be written in a folder on the FlexRip PC.

See the flavor-specific workflows for more in-depth information.

3.4.1.2 Native workflow

As well as being an Adobe Certified PS3 and PDF RIP, FlexRip can also rip data from all Esko PrePress applications without any additional calculation or processing time, since the format used in the Esko PrePress applications is exactly the same format used in the FlexRip. This enables an unrivalled level of throughput and consistency.

You can choose to print to the FlexRip directly from Esko PrePress applications like Esko PackEdge and Esko Plato and all output options can be set interactively. To maximize throughput, operators can rip files via a ticket-driven workflow (Automation Engine Server or FlexRip Pilot), offline from the graphical editors. Jobs can be selected, assigned a ticket and then launched in the background, reducing workstation time. Users can see the ripping progress of any job on either the Mac or Windows PC. Logging information can be obtained.

See the flavor-specific workflows for more in depth information.

3.4.2 Which file formats can be sent?

As the FlexRip is a certified PS level 3 RIP, following file formats can be sent:

- Separated PostScript: Level 1, 2 or 3.
- PDF 1.3 – PDF 1.4 – PDF 1.5 – PDF 1.6
- Esko's native file formats.

A normal PostScript workflow will only be based on **separated** PostScript, although FlexRip can handle composite PS files as well. The PostScript interpreter of the FlexRip will read composite PostScript, analyze it into separations and hand over the data of each separation to the RIP, which will make 1 output file per separation. However, customers that receive composite PDF files have to realize that errors may occur when handling the files.

Separated PostScript files for a FlexRip were made with a specific FlexRip PPD. Composite data may not be made via a FlexRip PPD and will probably miss some RIP settings, like the correct screen ruling (angle, LPI, dot type), output name, etc... Most of these then have to be set in the Dispatcher's queue settings. In the Screening tab, you can define the missing screen ruling parameters or overwrite the ones that are incorrect.

Note

In a PostScript workflow, Esko strongly recommends using separated PostScript as standard and preferred input channel.

Difference between composite and separate PostScript

In general, DTP applications output their data in the description language "PostScript" (PS). When the output has to be a color version (e.g. a proof), one will write "composite PostScript". This 1 file generally includes all the data, their color attributes and their relation to each other. Output for a specific proofer will be done using a PPD file (printer description) of that proofer, meaning that the PS file will be adapted for that specific output device.

When outputting to a film- or platesetter (e.g. CDI), the job has to be delivered to the RIP as a "separated PostScript" file. This means that all the data are already split up per separation (ink). This is also 1 file, but now written in chapters ('pages'). Each Chapter describes 1 ink. The RIP of the film- or platesetter will recognize these "chapters" and handles each ink separately. The color information in this file is in fact redundant info (the laser in the machine does not care about color); so each 'chapter' describes the separation in black.


Also **PDF** files may not contain the correct info. The correctness of the PDF files will heavily depend on the applications that write the PDF files. Very common mistakes, such as missing special colors or missing separation info (LPI/angle) are not limitations of the PDF format itself but of the applications that produce these PDF

files. PDF files written from Esko applications such as Esko PackEdge, Esko Plato and Automation Engine will contain the correct info.

3.4.3 Workflow description

FlexRip/Approval provides a front end for Approval XP Digital Proofing systems. Esko-native data or a PS, PDF, EPS, TIFF, TIFF/IT or DCS file are sent to the RIP, either via an Expose Ticket, or via the Print menu in the DTP application. FlexRip/Approval can be installed on the XP Host, or on a separate station (as in the below graphic) and outputs to a high resolution proofer from Kodak.

Introduction to an Esko FlexRip Workflow



3.5 What is a FlexRip Queue?

The heart of the FlexRip is a program called the **Dispatcher**. A Dispatcher controls the RIP and manages input queues for one specific device. Queues receive the PS data that were printed from the DTP station. The behavior of the queue ('how will it rip') is determined by its 'settings'. Each queue can have different settings.

There are several queue types. The most common are:

- An AppleTalk print queue (Macintosh)
- A Hot Folder
- A 'Named Pipe' queue ("PC-talk").
- An EskoLink queue

The FlexRip queue receives the data and rips it to an output file according to its specific settings.

4 Startup and shutdown of FlexRip

4.1 Why and when?

In any normal FlexRip workflow, the FlexRip computer should never be shut down. Even reconfiguring RIP queues does not require shutting down or rebooting the computer.

So why shut down the FlexRip?

- You expect a power failure.
- You physically want to move the computer.
- You have to open the computer (hardware service reasons).

Or why reboot the FlexRip?

- The Windows software asks you to. This will often be the case when re-installing Windows software or peripherals on the computer.
- Some (Esko) service intervention requires to do so (changes to configuration of the network, modem or display might require a reboot afterwards).

A Windows shutdown will automatically stop all running processes. This means that also all running Esko programs will be stopped automatically. We do advise you to separately stop all programs before rebooting or shutting down the FlexRip computer.

As the FlexRip is made to rip, and the RIP itself is a client process of the Dispatcher program, the most important program running on your FlexRip is the Dispatcher! This will also be further explained in detail.

4.2 How to start up a FlexRip?

4.2.1 Start up the computer

The FlexRip computer is switched off.

- Check the network cable.
- Switch the monitor on.
- Remove all floppy disks or CDs from their drives.
- Press the power button (top-left on front panel).

Windows will make your computer boot automatically. If you are not familiar with PC operating systems, never intervene during the boot process. The boot sequence

should end with a screen that has the window:

"Begin logon"

'Press Ctrl + Alt + Delete to log on'

If you wish to use the normal FlexRip software, log on as user 'FlexRip' with password 'FlexRip'.

Only log on as user 'Administrator' for Windows system-management reasons or to install software.

4.2.2 Starting up the Rip

Starting the Dispatcher program starts the RIP.

- Start up the "Dispatcher(s)" by double-clicking its desktop icon or by choosing the right Dispatcher via Start ⇒ All Programs ⇒ Esko ⇒ FlexRip Approval 12.0



- Start up the 'Status Monitor' in the Tools menu in (each) Dispatcher.
- Start up the 'History View' in the Tools menu in (each) Dispatcher.

More detailed info on these programs can be found further in their separate sections: Status Monitor (page 77) and History View (page 80).

Note

Renaming the desktop icon can only be done in the FlexRip Configurator. See the FlexRip Configurator manual for more information.

4.3 How to shut down a FlexRip?

4.3.1 Stopping the Rip

Closing the Dispatcher program stops the RIP.

Note

When stopping the Dispatcher program, it is always advisable to close its client programs Status Monitor and History View first.

How to stop the Dispatcher:

- Choose Exit from the Server menu and confirm by clicking Yes on 'Are you sure? Or simply click the close button (top-right in the Dispatcher window) and confirm with Yes on 'Are you sure? '.

4.3.2 Shutting down the computer

To shutdown the FlexRip computer:

1. Close all programs.

Other programs that could still be open:

- Curve Pilot editor
- Text editors Notepad or WordPad

2. Start ⇒ Shut Down. Choose 'Shut down the computer' and click YES.

4.4 How to reboot the FlexRip computer?

- Close all programs.
- Go to Start ⇒ Shut Down ⇒ Restart the computer and click YES. The computer will automatically shut down and restart again.

5 An overview of programs on the Esko FlexRip

5.1 General

Logged on as user 'FlexRip' (see next section for details on logon users (page 23)), you will probably find at least 3 icons on your desktop that start up following programs: the Dispatcher, Curve Pilot (Esko's Dot Gain Compensation editor) and FlexRip Configurator 12. If you do not find any desktop icons go via Start ⇒ Programs ⇒ Esko...

1. The **Dispatcher** is the 'heart' of the FlexRip. It is both the 'daemon' (continuous automatic process) that makes the RIP run and the place where all queues and RIP options are set up.
Each output device requires a new Dispatcher. This means that if you make files for 3 different output devices, you will have 3 Dispatchers.

Note

Note that each Dispatcher needs a separate licence.

2. The **Status Monitor** is a dedicated monitor of the Dispatcher processes. This Monitor is opened from within the Dispatcher Tools menu.
It is recommended to activate the Status Monitor immediately after starting up the Dispatcher. Starting up the Status Monitor after having launched a job will not immediately show the actions of the job that is being ripped.
3. **History View** lists the finished processes and their log files. History View is opened from within the Dispatcher Tools menu.
4. **Esko Curve Pilot**: this DGC (Dot Gain Compensation) editor offers you the possibility to make the compensation curves that are necessary for specific printing processes (e.g. flexo). The strategies (the curves, *.icpro files) will reside on the FlexRip or the Automation Engine server.



Note

Curve Pilot is further explained in a dedicated Curve Pilot document that can be found on your Esko Software Suite12 DVD.

Note

Curves for the CDI or Automatic PlateMaking curves can be created in the FlexRip Configurator.

5. The **FlexRipConfigurator** allows you to add, modify or delete configurations.



Note

You should be logged on as 'Administrator' to be able to use the FlexRip Configurator.

5.2 Which logon to use?

- When do you log on as user **Administrator**?

When you are installing or removing software or configuring your FlexRip computer on Windows level (networking, connectivity etc).

- When do you log on as user **FlexRip**?

In all other cases. All daily use of your FlexRip: the Dispatcher or its queue management, Esko Curve Pilot, Esko Bitmap Viewer.


The following sections cover the Dispatcher (page 24), Status Monitor (page 77) and History View (page 80) in detail.

6 Dispatcher

6.1 General

The Dispatcher program is used for:

- Starting and stopping the Rip
- Setting up input queues and their Rip options



The Dispatcher is started by:

- Double clicking the icon on the desktop.
- Clicking Start ⇒ Programs ⇒ Esko ⇒ FlexRipApproval 12.0 ⇒ FlexRipApproval Dispatcher.

This starts up the Dispatcher program itself, but also puts the actual RIP in an 'idle' status, which means stand-by for action.


Warning

When the Dispatcher program is stopped, all ripping processes stop executing and the RIP itself is stopped.

When an ongoing RIP process has to be stopped for some reason, then choose 'Abort job' from the Server menu. This stops all ongoing RIP processes, but leaves the Dispatcher program alive. As soon as you send a new job to the RIP, the RIP will start up automatically. When the Dispatcher is started for the first time, there will be

at least 4 queues visible, one of each standard type. FlexRip/B will start up with only one queue, the EskoLink queue.

6.2 Rip menu



The Server menu contains the following items:

1. Clear History (page 25)
2. Send Job(s) (page 25)
3. Abort Job (page 26)
4. Restart PS Rip (page 27)
5. Exit (page 27)

6.2.1 Clear History

Choosing *Clear history* will delete all messages in the History View selection. You will be asked to confirm first. As this deletes all entries in the history database, they cannot be retrieved. This 'cleaning' will also delete the corresponding RIP log files.

Note

It is normally not necessary to clear this history database manually. In the Options menu

⇒ Program Options, you will be able to set a limit for the amount of history entries that have to be remembered. If this number is exceeded, the oldest entries are removed automatically.

Tip

It is advised not to enter a high number for the amount of history entries. The higher the amount of entries allowed, the slower the History View and RIP logging will function.

6.2.2 Send Jobs


Click *Send Jobs* to open the 'Select and Send Jobs' dialog. Here you can browse to the

job you want to send.

Note

This will only work if a Hot Folder is selected in the Dispatcher.

You can also right click the selected Hot Folder queue to make the Select & Send Job(s) dialog pop up.



6.2.3 Abort Job

As explained above, *Abort Job* stops the RIP (and as a consequence any current ripping process). Remember that the RIP is automatically started again as soon as another job comes in. You could choose to abort a job when you are sure you do not need the output (e.g. you know the input file was wrong or a mistake was made in the queue options).

Output files that were already generated by the RIP are not automatically removed.


6.2.4 Restart PS RIP

When Japanese fonts are downloaded, *Restart PS RIP* allows restarting the PS engine of the RIP to activate the fonts in the RIP.

6.2.5 Exit

This will stop the Dispatcher program (and the RIP). Clicking the close button of the Dispatcher dialog will have the same effect. You will be asked to confirm first.

6.3 Options menu




The Options menu contains the following items:

1. Program Options (page 27)
2. Queue Defaults (page 29)
3. Performance (page 30)
4. Rip Priority (page 30)

6.3.1 Program options

The program options are general Dispatcher settings. They can be set per Dispatcher.



6.3.1.1 FlexRip Log Files

You can decide here whether or not you want the RIP to create log files. They can be interesting to find out what happened if something went wrong. It is advised to always create log files. Log files can be viewed in *History View* and are physically located in the *Logging* folder.

C:\Esko\bg_data_FlexRipapproval_v120\approval\Logging.

6.3.1.2 Automation Engine Server Disk Mounting

Enable *Dispatcher mounts disks* unless specifically mentioned otherwise.

6.3.1.3 Trace messages and History

- *Save Dispatcher Messages*. It is advised to activate this toggle. 'Trace messages' keep track of the general status of the Dispatcher. Esko will only consult these in case of problems.
- *Number of files used* indicates the maximum number of trace files that will be stored.
- *Maximum number of messages in each file* indicates the number of entries that

will be stored in one and the same trace file.

- *Number of entries in History* indicates the number of log files History View will show you. The number of entries in the History can be set as wished. 500 will probably be enough. This means that when entry number 501 appears, entry number 1 will be deleted.

6.3.1.4 Input Queue Settings

- *Include Debug Options*: When checked, an extra tab sheet in the default queue settings will appear: 'Debugging'. Please activate this Debugging (page 71) tab, because it enables you to control the contents of the log files. This is especially interesting for fast troubleshooting by customer services. They will advise you which settings to change in order to speed up problem solving.
- *Include Tuning Options*: Should not be active (again unless Esko Customer Service asks you to activate it).

Enabling the Tuning options makes a number of extra tabs appear in the Queue Settings:

- CopyDot Tuning (page 72), which is explained further on.
- LineWork Tuning
- Contone Tuning
- Memory Tuning

Note

Linework, Contone and Memory Tuning are specific tabs for our Customer Service department and may only be used to solve or find a workaround for a specific customer workflow or FlexRip problem.

- *Units*: Can be set to INCH, CM, MM or MIL (1000 MIL = 1 Inch).

6.3.1.5 Advanced

Capture PostScript file: This should not be activated unless Esko Customer Service asks you to. When activated, then after ripping every PostScript file together with a lot of extra information will be stored in a special folder as an extra text file. This is not the same as keeping the PostScript file in a Hot Folder after ripping! See further in the appendix: Some classic errors and their explanation (page 94).

6.3.2 Queue defaults

A FlexRip can have several queues of:


- different types
- the same type

Each queue will have its own settings (how to rip, where to write the output file...). The settings in *Queue Defaults* however are valid for all queues. We refer to the Queue Settings (page 42) chapter for more details on queue settings. (The different tabs look exactly the same).

The priority of the settings (page 42) is described further on.


6.3.3 Performance

This panel was used to overrule the default scheduling behavior of the Windows operating system. Recent Windows versions do this very good by default, so we no longer allow to overrule this.




6.3.4 Rip priority

This field allows you to set the priority of the ripping process over other processes. You might for instance have noticed that changing queue settings (working with the interface of the Dispatcher) is very slow when the FlexRip is ripping at that same moment. That is because the RIP process (the kernel) had all the priority. Now, some customers will want to use applications on the FlexRip a lot (working with Dispatcher, Esko Curve Pilot, Esko Bitmap Viewer) and some almost never. The recommended setting is Normal.



6.4 Tools menu



The Tools menu contains the following items:

1. History View (page 31)
2. Status Monitor (page 31)


6.4.1 History View

The Dispatcher program itself will not show you the list of actions that are finished. *History View* will. All further info on the History View (page 80) program can be found in a separate section.

6.4.2 Status Monitor

The Dispatcher program itself does not show any detailed information on the ripping action. The *Status Monitor* program of that Dispatcher will show you more. All further info on the Status Monitor (page 77) can be found in a separate section.

6.5 Info menu



The Info menu contains the following items:

1. Ports (page 32)
2. About Dispatcher (page 32)

6.5.1 Ports

The Dispatcher is the server program of the Status Monitor and History View programs. The Dispatcher ports are used by its client applications to be able to communicate with the Dispatcher. Technically they are TCP/IP socket port numbers.

6.5.2 About Dispatcher

Shows the date and version number of the Dispatcher program. This is useful information when reporting some problem with Dispatcher. It is NOT the version of your FlexRip software (see FAQs).

6.6 Connected monitors

The Tools menu allows you to start up a History View or Status Monitor of that (specific) Dispatcher. Both are actually client processes of that Dispatcher and count for a 'connected monitor'.

As there is no need to start up a History View or Status Monitor a second time, you will mostly see that the number of connected monitors is 2. If you see a number over 2 then you probably already started up these client programs and 'minimized' them. This indicates that this number is only there for your information.

6.7 Input queues

First we have a short look at the possible queue types and then a closer look at their settings.


6.7.1 Possible queue types

- **AppleTalk:** From Snow Leopard onwards (Mac OS X 10.6), AppleTalk is no longer supported on Mac. The preferred solution now is to use Esko Shuttle functionality to directly send files to the EskoLink channel of the Dispatcher.
-
- **Hot Folder:** A FlexRip Hot Folder is a folder on the FlexRip station that is mounted/shared (made visible) to other computers on the network. The DTP operator will print 'to file' and save the file directly in this Hot Folder. See also the section in the appendix 'How to mount FlexRip volumes on a Macintosh? (page 113)'.
- **Named Pipe:** From Windows Vista / Windows Server 2008 onwards, our Named Pipe workflow no longer works (as it relies on an Adobe kernel printer driver, and kernel printer drivers are no longer supported). The preferred solution now is to use Esko Shuttle functionality to directly send files to the EskoLink channel of the Dispatcher.
- **EskoLink:** 'EskoLink (or previously 'BarcoLink' or 'DigiLink') is a queue that represents a link with an Esko Server (Automation Engine or FlexRip Pilot). This kind of queue will 'receive' RIP requests for Esko native files.

6.7.2 New - Queue Info - Delete


Should you have deleted the only queue of a specific type, (e.g. you deleted the only AppleTalk queue present) then click the line below the other still existing queues (so no specific type is selected), and then click 'New'. The Create Queue window will pop up, allowing you to select a particular type of queue.

These three types of queues are PostScript channels. They cannot be used for Esko-native files.




For an AppleTalk queue you can only set the name and priority. Two situations are possible:

1. You create a new queue that is a **copy** of an existing queue. Here you can either use the queue settings of the queue copied, or you can take the default queue settings. Activate or deactivate the toggle to specify your choice.




2. You create a completely **new** queue.




The default queue settings option is greyed out, since these settings will automatically be taken. As this queue is no copy of an existing one, no settings can be copied.

For Hot Folder queues, apart from the name of the queue, the folder also has to be set up. For more information, see the next chapter: General (page 37).




For Named Pipe queues, two situations are possible:

1. You create a new queue that is a **copy** of an existing queue.
Here you can either use the queue settings of the queue copied, or you can take the default queue settings. Activate or deactivate the toggle to specify your choice.




2. You create a completely **new** queue.
Please give it a short name, preferably in one word: e.g.: Flexpipe. The

default queue settings option is greyed out, since these settings will automatically be taken. As this queue is no copy of an existing one, no settings can be copied.



6.7.2.1 General



1. **Name:**
Give your Hot Folder queue a logical name. The operators will then have a clear idea what the nature of the output will be. As seen in the above graphic: the name of the Hot Folder already shows that the file is ripped at 2400 ppi. So it is advisable to 'summarize' in the name of the queue the 'hard' queue settings that influence the output (as these queue settings will overwrite the settings in the PostScript file).
2. **Folder:**
Type in the correct path of the folder on the FlexRip that will serve as Hot Folder.

Note

Create the actual Hot Folder (using Windows Explorer) before you start creating the Hot Folder queue.

Note

On Windows level, you could delete a folder that is used by a Dispatcher queue as the actual Hot Folder. When this happens, the Dispatcher will detect that the construction of this Hot Folder is no longer valid. When you consult its 'queue info' and click 'OK' following warning will appear:

"New Folder"

The Folder 'name' does not exist.

3. Activate:

Checking the box activates the folder as Hot Folder. A de-activated Hot Folder will not rip incoming files automatically.

4. Scan Interval:

This indicates the period after which the Dispatcher checks the Hot Folder for incoming files.

Note

If you are scanning Hot Folders over the network, you should decrease the frequency of which the Hot Folder is scanned, otherwise you might create unnecessary network

activity. In other words, if your Hot Folder does not reside on the FlexRip, increase the number of seconds.

5. Queue Priority:

The RIP will (only) consult the priority settings when several jobs are waiting to be ripped. While the first job is being executed the RIP will consult the queue priority setting to decide which one to rip next.

Example:

When the RIP is processing a job in queue A, and both queue B and C have a job waiting to be ripped, then the queue with the highest priority settings will have its

PostScript file ripped next (e.g. B has priority 3, queue C has priority 2.

When queue A has finished, the job in queue C will be next).

6.7.2.2 File handling

1. Trigger on file type:

Select the file types you want the Hot Folder to trigger on and put them in the 'Trigger on File Type' column. Move the extensions from the right to the left column by clicking the << button. If you do not specify file types in the 'trigger' column, the RIP will start up for any incoming file, regardless if this file can be processed or not.

PDF* stands for all types of Esko PDF Native files (PDF, PDFPLA, PDFSTA,...)

2. Keep files with unknown file type for x seconds in Hot Folder:

File types you told the Hot Folder not to rip are best not kept in that Hot Folder. These unknown file types will be moved automatically to the subfolder named 'error'. Determine after how many seconds you want them to be removed. The maximum value here is 1800 seconds (30 minutes).

3. Remove file after imaging:

When the option is not activated, the PostScript file will stay in the Hot Folder after it has been imaged (in an appropriate subfolder named 'OK'). If you want to use the same PostScript file for imaging on other devices via other FlexRip flavors you should not activate this box. If it is active the PostScript file will be deleted and you will need to make a second PostScript file for the other devices.

Note

This is only about known files that have actually been ripped. Not having these removed (deleted) after ripping means they will be automatically moved to the subfolder OK or Error.

4. Take Drag & Drop Files:

makes it possible to drag and drop files onto a Hot Folder that is defined in the FlexRip Dispatcher. It is also possible to select and send an (E)PS/PDF file to a Hot Folder from the FlexRip itself. Checking the 'Take Drag & Drop Files' box prevents you from actually having to drop the files into the defined Hot Folder before the file would be ripped. Files can be selected from any folder visible from Windows Explorer. To activate this mechanism:

1. Click the Hot Folder to highlight it.
2. Click Queue Info.
3. Activate Take Drag and Drop files.
4. Click OK.

Note


It is only possible to activate this 'Take Drag & Drop files' feature for 1 Hot Folder at a time.

To select (E)PS/PDF files to be ripped on this Hot Folder using the Windows Browser:

1. Click the Hot Folder to highlight it.
2. In the Dispatcher, select Send Job(s) from the Server menu or click right and select Send Job(s) from the pop-up menu..
3. Browse to the job(s) and click Open.

The selected files will be copied automatically to the Hot Folder and will be ripped normally.

5. OK/Error Folders:




The settings above allow you to either keep the incoming files after ripping or to remove them. If you decide that files should be kept after ripping it is advised to define exactly to which folder you want them to be moved. Per Hot Folder, 1 folder can be specified for all files that went through the FlexRip successfully and another folder for those files that errored out or were aborted by the user. To define these folders:

1. Click the Hot Folder and click the Queue Info button.
2. Now click the OK/Error Folders... button

Note

This button will be greyed out when the Remove file after imaging option is activated.



3. Select 1 folder for the files that went through the FlexRip successfully (OK folder) and 1 folder for the files that errored out or that were aborted by the user (Error folder). Note that before you specify the folder of your choice, the default folder is defined.

Note

It is advised not to put the processed files in the Hot Folder.

4. When specifying the folder name you can browse to it or you can type in the name of your folder. If the folder you specify does not yet exist the system will ask if it needs to be created.

Note

These fields cannot be left blank.



7 Queue Settings

Many of the settings that are explained hereafter can also be set as print options can be set in the Automation Engine or FlexRip Pilot for Esko-native workflows and in DTP applications for PS/PDF workflows. But then, which settings will the RIP take into account? What if opposite settings occur? And what if options are not set? The next section explains how different settings interact.

7.1 Priority of settings

When an operator has set specific options, the file ends up in a Dispatcher queue that also has its specific queue settings, and possibly also extra settings in the 'default settings' window. Which RIP settings will then be taken?

This is the order of how the RIP consults the settings:

1. **FIRST: Dispatcher: specific Queue Settings.** Queue settings will overrule all others. Settings you always want to apply should be set here. See the section 'Workflow: flavors and hints' for an important remark on the settings 'image' and 'emulsion'!

Note

Options that are set in the Dispatcher Queue Settings will be greyed out in the server tickets.

2. **SECOND: settings in the ticket or PostScript file.** On this level you can set the options that are job-related. In an Esko native workflow, the settings in the ticket will be taken. In a PostScript workflow, settings in the Print menu, using the correct PPD, will be used.
3. **THIRD: Dispatcher: (menu 'options') Queue Defaults.** Queue Defaults are settings that apply to all queues. The RIP will only consult them if options are not set in the Dispatcher or the ticket/PostScript file. This means that they are only executed in case there is still a "none" setting to be answered! If a "none" settings is still not answered by the Queue Defaults, the default setting inside the FlexRip software will be taken.

Tip

To set up a logical workflow, it is advised to set the options that are always applicable as high in the order as possible as these will overwrite occasional mistakes in ticket or print settings.

Example: You always want to expose on a device at 2000 DPI. Then enter the resolution setting in the Queue Settings. As soon as a setting is required only

from time to time, you might consider:

- to put it in the name of the (newly made) specific queue.
- to leave the (default) queue settings on 'none' and specify it (each time when wanted) in the ticket or PostScript file.

Note

A number of options, like output path and (scr)dgc can also be set in the **FlexRip Configurator**. These settings will overrule all settings mentioned above! To make you aware of Configurator settings, options that are set in the Configurator are greyed out in the Dispatcher, ticket and Queue Defaults.

7.2 Basic

The Basic options allow you to decide on how the output should look.

Queue Settings: Hot Folder

Screening | PS | PDF Input | Curve Pilot | Debugging

Basic | Output | PS | PDF Marks | Advanced Options

General

Device Type: FlexRip->Approval

Device Name: KODAK_APPROVAL_XP

Resolution: 2400

Rotation: (none)

Page Size:

InputJobSize | Width: 0.0 | Height: 0.0

Oversized Image: Error & Stop

OFE Details

Host Name:

Imaging Options

Dotshape: (none)

Laydown order: On Final Substrate

Laydown Options: (none)

Mirror: (none)

OK Cancel Apply

Warning

Do not enter 0 (zero) in a value field. It will be considered as a 'hard' value and possibly overwrite others! Leave the value field 'empty' before clicking OK.

7.2.1 Device type

This shows the type of Output module this specific Dispatcher was made for. Each Dispatcher is based on a specific 'fid' file. A fid file describes a machine type (device, printer description), which is why specific resolutions and size options will appear in the dropdown lists.

7.2.2 Device name

Select the Approval machine connected to this RIP. Choose between KODAK_APPROVAL_XP4 or KODAK_APPROVAL_XP.

Note

If configured correctly, this option is set correctly when you start the Dispatcher for the first time.

7.2.3 Resolution

Here you can specify the expose resolution of the job. The values in the dropdown list are specified in PPI (Pixels Per Inch). The resolution chosen here will be identical to the resolution the file will be exposed with. This field should be set to (none) if the decision is left to the operator.

Note

If configured correctly, this option is set correctly when you start the Dispatcher for the first time.

7.2.4 Rotation

For PS/PDF or native input (Hot Folder, AppleTalk or Named Pipe) it is possible to preset a rotation.

7.2.5 Page size

Determines the size of the output file. It is also advised to leave this on 'none' as the output file is best the size that was determined in the application.

Warning

Never leave it on Custom page size, which takes the maximum size for that device. This means that it will always create output files as big as the drum surface.

Selecting an option specific to a machine, meaning that output files will be created as big as the media size, will considerably slow down the data transfer to the machine.

Note

For FlexRip/Approval it is advised to select InputJobSize as the output file size, since this represents the size that was determined for the job output in the application. When you select InputJobSize the width and height field will show as zero.

7.2.5.1 Oversized image

Here you can specify the policy to follow when the image is oversized. The default setting is none, meaning that a job will error out when it is oversized.

Other options are:

- Center horizontally & clip: the job is positioned in the center. Excess information will be clipped.
- Clip at maximum size: the job is positioned in the top left corner. Excess information will be clipped.
- Error & stop: the RIP will give an error message and will stop ripping.

7.2.6 OFE details

By default, the machine name of the OFE host should be displayed in the input box. If this is not the case, enter the correct name.

7.2.7 Imaging options

7.2.7.1 Dot Shape

Choose your dot here. When set to 'none', the dot shape in the PostScript file will be used.

For more information on Esko's dot types, we refer to the Screening and Curve Pilot documentation you'll find on the Suite 12 DVD.

7.2.7.2 Laydown order

This option allows you to invert the laydown order of the inks. This can be interesting when printing on transparent sheets.


- On final substrate
- On intermediate

There are different places where you can see the order of the inks. It is practice that some people talk about the ink order as XP host (Intermediate) as reference, where as some others take final proof as the reference. With this laydown order reference option in FlexRip/Approval, you can specify what is your reference is before specifying laydown order options.

Supported references are: On Intermediate or On Final Substrate. FlexRip will use this option as a reference for all its laydown order calculations. The option 'On Final substrate' is the default. 'On Intermediate' option is useful if you have a recipe list from FastRip/Approval V5.1 or using the recipe list from another Rip, which has a recipe definition based on XP host as reference. Please note that when you use the 'On intermediate' option, your design, the recipe definition and laydown order option have to be made using intermediate order as your reference. E.g. when your reference in intermediate the white ink should be last in your design. Best practice is to use 'on Final substrate' as reference and make your design as explained in the chapter below.

7.2.7.3 Laydown options

Making a proof on Approval machine involves many steps. After ripping, the bitmaps are sent to the XP host with a specific order. The machine will print these bitmaps on to an intermediate sheet as it is specified by the Rip. Once the intermediate is ready, it is laminated to the material of your choice. The final substrate can be paper, transparent sheet, metal etc. The ink order you see in your XP host is not the final order! The order will be inverted when you laminate the proof to your final substrate. The following block diagram explains this concept in detail:



The concept is that you can use the same file for both printing and proofing. In an Esko workflow you make your design in the way you want it to be printed on your press and proof the same job to FlexRip/Approval to get your proof.

Note

Please keep these things in mind when working with lay down order

- *The ink order you see in your XP host is not the final order! The order will be inverted when you laminate the proof from intermediate to your final substrate.*
- *Silver and White DW01 donors are opaque in nature! You should be careful with ink order when using these donors in RECIPE definition.*
- *When using white as background, make sure that is the first ink in your design.*

For customers working with PostScript workflows more options are added to control lay down order.

Supported options are:

1. Keep the ink order: Keep the order as in the job. This is the default setting.
2. Invert the ink order: Invert the ink order. It is mainly used when proofing on transparent media.
3. Process inks first: Places CMYK inks first on the proof.
4. Inks using White donor first: Ink defined with White DW01 donor is placed first on the proof. Useful, when white is used as background.
5. Inks using White donor last: Ink defined with White DW01 donor is placed as last color on the proof.
6. Inks using Opaque donors first: Inks defined with either white DW01 or Silver is

placed first on the proof. If one ink uses White and other uses Silver, then Ink using white donor will be proofed first.

7. Inks using Opaque donors last: Inks defined with either white DW01 or Silver is placed last on the proof. If one of the inks uses White and other uses Silver, then Ink using white donor will be proofed last.


Other than the ink based laydown order approach, is controlling laydown order based on a predefined donor order. In the Laydown order tab of your configuration, you could specify the donors in the order in which you want it to be printed on your final substrate. FlexRip will then follow this order. Please note that this donor based laydown order only works together with 'Optimize Media' option.

7.2.7.4 Mirror

This option allows you to mirror the job.

This can be interesting when printing on transparent sheets.

7.3 Output



7.3.1 Location & Name

7.3.1.1 Output location

The location of the output folder(s) for the temporary output files is free to choose. It is logical to define the output folder(s) on a hard disk with enough space available (often drive D:\ on a FlexRip).

Tip

If you want several output folders, then it is a good idea to create them under one general output folder. So, after making the top folder visible to other computers, any new folder under that top folder will automatically become visible as well.

Note

There are different places where you can specify the required output location. If the output path is specified in the FlexRip Configurator (which has the highest priority), the output path will be greyed out in the Dispatcher, ticket and Queue Defaults.

Example

D:\output

Is the 'top' folder

This folder is not used as a real output folder.

D:\output\komori_urgent

D:\output\komori_normal

are actual output folders that contain the output files. The operator will already see which output files are urgent and on which plate type they should be imaged.

Note

Select the actual folder by using the Browse button, before filling in its path here.

The location of the output folder for temporary files is free to choose. These files are used by the RIP to send files to the proofing system. They can be removed automatically if the Delete temporary LP files (page 51) toggle is checked. If you do not specify an output path, the RIP will write all files to the default output directory i.e. ...\\Esko\\bg_data_FlexRipapproval_v120\\approval\\Tmp.

7.3.1.2 Output file name

Note

This option is not applicable to FlexRip/Approval and FlexRip/B.

7.3.1.3 Restricted file names

Note

This option is not applicable to FlexRip/Approval and FlexRip/B.

7.3.1.4 Delete temporary LP files

By checking the box you can indicate whether or not you want the application to delete temporary LP files after exposure. It is advised to always keep the option checked.

7.3.2 Configuration set

7.3.2.1 Name

Specify the configuration you want to use.

Configurations are created in the FlexRip Configurator. For more information, please refer to the Configurator documentation on the Suite 12 DVD.

7.3.2.2 Media saving

The media saving option allows you to save on donor sheets in the Approval machine.

Three options are available:

1. *Optimize media*: The machine will use the maximum possible optimization, i.e. the fewest donor sheets.
2. *Optimize media keeping recipe order*: The machine will optimize the media, keeping the recipe order into account.
3. *Do not optimize media*: For each separation, a new donor sheet will be used.

An example will make this more clear.

Do not optimize:

With 'Do not optimize', each separation results in a separate donor sheet. In this example, 8 donor sheets will be created.

C	→	C	1 donor sheet
M	→	M	1 donor sheet
Y	→	Y	1 donor sheet
K	→	K	1 donor sheet
485	→	M, 1, Y, 2	→ 1 donor sheet for M 1 donor sheet for Y
Gold	→	Silver, Y	→ 1 donor sheet for Silver 1 donor sheet for Y

Optimize media:

The best possible optimization will be pursued. Here, this results in 5 donor sheets. C, K, and Silver are mapped to their respective donor sheets. The magenta donor sheet will be used for the Magenta separation and the magenta from 485. The yellow donor sheet will be used for the Yellow separation, yellow from 485 and yellow from the gold separation.

C	→	C	1 donor sheet
M	→	M	1 donor sheet
Y	→	Y	1 donor sheet
K	→	K	1 donor sheet
485	→	M, 1, Y, 2	→ M will be proofed, using the same donor sheet as the Magenta separation Y will be proofed, using the same donor sheet as the Yellow separation
Gold	→	Silver, Y	→ 1 donor sheet for Silver Y will be proofed, using the same donor sheet as the Yellow separation

Optimize media keeping recipe order:

If you work with opaque inks, like Silver in this example, the recipe order is important. To obtain Gold, the silver separation should come first, followed by the yellow separation.

The number of donor sheets will be reduced, but not to the minimum. In this case, 6 donor sheets will be used. The recipe order is taken into account.


C	→	C	→	1 donor sheet
M	→	M	→	1 donor sheet
Y	→	Y	→	1 donor sheet
K	→	K	→	1 donor sheet
485	→	M, 1, Y, 2	→	M will be proofed, using the same donor sheet as the Magenta separation Y will be proofed, using the same donor sheet as the Yellow separation
Gold	→	Silver, Y	→	1 donor sheet for Silver 1 donor sheet for Y

7.4 PS/PDF Input

Warning

FlexRip 12 requires a new PPD. These PPDs are included on the Suite 12 DVD. The new PPDs reflect the changes in the FlexRip architecture and update Adobe libraries that interpret the incoming PS/PDF files in FlexRip 12.

*Please note that the PPDs that were used in FlexRip 5.2 will **not work** in FlexRip 12!*



7.4.1 PostScript

7.4.1.1 Screen type

Enable the appropriate screen type. You can choose between: Esko Classic, DynaCell, PostScript or none.

- *Esko Classic (Precalculated)* means that the aspect, the form, the rulings and the angles of the screen are pre-defined in the Esko screening labs. These screens are the result of advanced engineering work. The screens are optimized for a smooth aspect, good behavior on the different printing processes, lack of artifacts etc. Furthermore, the screens are designed following a system of screen angles that avoids moiré between the main colors (cyan, magenta and black). The use of precalculated screens allows supporting advanced screening features like stochastic screening (Monet Screens) and transitional screening (SambaFlex Screens). Precalculated

screens have only one disadvantage: since they have been designed and tested one by one, there is only a limited number of them available. Although the total number exceeds 2000 different screen ruling/angle/dot shape combinations, it is very well possible that no precalculated screen is close enough to a customer's wish. This happens specifically when other angles than flexo or offset angles are demanded. A typical example is silk screen printing where unusual angles and screen rulings are used to avoid clashes with the silk screen mesh. Esko DynaCell technology was developed particularly for this purpose (see below). The pre-calculated sets are also made to provide maximum protection against moiré. For more information, please check the Screening manual.

- Using *PostScript* screening implies that all the information needed to build up the dots has to be in the PostScript file. Combining PostScript screening and Esko screening in the same file and/or separation is only possible using the optional ScreenFilter application. Please see the documentation on the ScreenFilter for more details.

In every DTP application, you can choose the LPI from the Esko PPD or you can overrule it. Also the print angle will be offered by the PPD but the DTP applications permit you to enter other angles. If you send these data to the RIP, the 'Esko screening' setting will again change these values via its own 'jump-to' mechanism. This means that the RIP will automatically jump to the nearest LPI or angle that is supported. If you do not use 'Esko screening' but 'PostScript screening', these 'special requests' will indeed be realized by the FlexRip.

If you activate PostScript screening, the dot shape should also be described in the PostScript file. If you cannot select dot shapes in your DTP application, then it will probably describe the standard Fogra Round dot shape (see also Esko's Fogra Round).

Why ever use this?

You could for instance use this if you insist on some 'exotic' angle. With exotic we mean an angle which is not standard in flexo/offset. If you need an angle of 3 degrees, then this is the only way to get it in the output file. Then of course you will be limited to the dot types that your DTP application offers you (to write in its PostScript output).

- If the *DynaCell* license is available, this FlexRip option allows the operator to specify any angle or lineature combined with Esko screening. It is particularly useful for screen printing. DynaCell differs from Esko Classic in that it doesn't use sets of precalculated screens. Because of this, DynaCell offers no protection against moiré. Esko Classic screening does, as this screening only allows moiré free combinations of resolutions with LPI and angles.

For more information on DynaCell, please consult the Screening manual.

Note



Because of the nature of Monet screening and SambaFlex screening it will not be possible to use DynaCell technology with these two screens. If DynaCell is selected together with one of these screens an error will be generated at rip time.

7.4.1.2 Screen Swap Table

Note

The Screen Swap Table option will only be activated if screened data is output.

ScreenFilter allows you to define screen swap tables so that when files, containing e.g. PS dot shapes, come into the Esko system the information of the screening is not lost.

1. In the Screens part , all detected, but unregistered screens appear. You can register them and use them to define screen swap tables.
2. In the Screen Swap Table part , you define screen swap tables, these can be used in other applications, such as Esko PackEdge, Esko Plato, FlexRip, Automation Engine, ...

For more information on how to create ScreenFilter rules, please refer to the ScreenFilter documentation.

Note

Selecting (none) creates a FlexRip v5.1 like situation.

7.4.1.3 Pure black overprint

Set the overprint mode for objects containing 100% black only. Possible Pure Black overprint modes are:

- No: no overprint is forced on an object containing 100% black, which means that the situation is as is defined in the job.
- Yes: forces PostScript overprint for objects in 100% black.
- None: the default Queue settings will be consulted.

7.4.1.4 Enable optimization

Should be set to 'Yes'.

Example

Esko's RIP kernel will see to it that the vignette quality is enhanced.

Note

This optimization is not relevant when the vignettes are described as CTs in the PostScript file (as is mostly the case with ArtPro jobs).

7.4.1.5 Preserve Quark trapping

If set to 'Yes', the Preserve Quark trapping option forces the system to keep the trap strokes made by QuarkXpress.

7.4.1.6 Ignore PS color management

Images can be saved in PhotoShop in EPS format using an option 'Use PostScript Color Management'. The result of this operation is that the resulting EPS file contains information that the pixel values are not simply RGB or CMYK but are to be interpreted by the receiver as a CIE-ABC or CIE-DEFG image and that the receiver should reconvert that image to its own colorspace using a PostScript CRD.

In most cases this 'Use PostScript color management' option was set by accident and the image retoucher did not intend that his carefully retouched image would be reconverted from 1 color space to another changing all the separations. When this option is off, PostScript color management is applied and the image is run through a CRD, if this option is off the original data is interpreted as deviceRGB or deviceCMYK even if the EPS file specifies that PS color management should be used. Remark that PS color management is always used for Lab images even if this option is switched on.

This means that if this toggle is checked, the color management that would be applied to included PhotoShop EPS images will be ignored.

7.4.2 PDF

7.4.2.1 PDF password

In case you send PDF files that include a password, unlock them by entering the password here.

7.4.2.2 Ignore calibrated colorspaces

When this toggle is checked, FlexRip will ignore [CIE based] calibrated colorspaces and will replace them by their regular device-independent counterparts.

The color of objects like lineart and images can be defined using a calibrated colorspace. This can happen because the objects already have a color in a calibrated colorspace before distilling or they can acquire a color in a calibrated colorspace during distilling process. This is not always intended behavior and the 'Ignore Calibrated Colorspace' option will ignore the calibrated colorspace of such objects when converting the file to GRS. A typical example is that when you have black objects in a calibrated colorspace, you risk ending up with CMY color components if you do not ignore the calibrated colorspace.

7.4.3 Images

7.4.3.1 Abort for images with scaled resolution below ... dpi


Checking this toggle makes sure a resolution check on incoming images is performed. This option offers you the possibility to get the RIP abort the job if images below a certain minimum resolution are found. The resolution is calculated after scaling (effective when placing the image, including a possible global RIP scaling) and is a very solid quality check before a bad plate or film is made.

7.5 Native Input

When bitmap images are present in the job, they will only be contoured if the output resolution is not equal (or is not a multiple of) the resolution of the bitmap image or if the bitmap image is rotated over an angle that is not a multiple of 90 degrees. In case of correct expose resolution and no rotation the bitmap image will be treated in an optimized way (direct access to the image for direct exposure).

Note

This is only for an EskoLink workflow, using Esko native file formats (PDF, PDFPLA, PDFSTA,...).



7.5.1 Screening

Possible settings:

1. (none)
2. DynaCell
3. Esko Classic (precalculated)

DynaCell allows you to use any angle and any LPI at any resolution. See the Screen type (page 55) section in the PS/PDF Input chapter for more information about the different options.


Typically, this option is set to **(none)**.

7.5.2 Abort for images with scaled resolution below... dpi

Checking this toggle makes sure a resolution check on incoming images is performed. This option offers you the possibility to get the RIP abort the job if images below a certain minimum resolution are found. The resolution is calculated after scaling (effective when placing the image, including a possible global RIP scaling) and is a very solid quality check before a bad output plate or film is made.

7.6 Curve Pilot

The Curve Pilot tab allows you to specify press dot gain compensation, assuming that the plate dot gain compensation will be specified in the FlexRip Configurator, attached to the media selected in the configuration used.



7.6.1 Press dot gain compensation

The Press Dot Gain Compensation group allows you to specify a 'single curve' DGC and/or an 'automatic' compensation strategy from the SCRDC's, ICPRO's or .PRSYNC's available in the list.

For more information on how to create dot gain compensation files, please see the dedicated Curve Pilot documentation on the Suite 12 DVD.

What if you specify both a dgc (single curve) and a scrdc or a Strategy/Curve Set (automatic compensation)?

Then the curves are executed in a specific order: first the scrdc or Strategy/Curve Set, then the dgc. This also happens when e.g. a dgc curve was specified in the Macintosh print menu and a scrdc curve or a Strategy/Curve Set was set in the Dispatcher's Queue settings. The first one is not executed in the PostScript file but written as a reference in that PostScript file, the same way as a scrdc or a Strategy/Curve Set selection in these queue settings is also a reference to the rip. Why you have to specify a separate scrdc/dgc curve or a Strategy/Curve Set is explained by the FlexRip instructor. To a large extent, this depends on your previous and current workflow. The Curve Pilot documentation is a good guideline to help you answer these questions. To get a good idea of what exactly happens when you use both tools, just make a drawing of the 2 curves: put the scrdc first, the dgc curve next to it and follow what happens to a specific percentage.

7.6.2 Calibration


When the output device is not linear (i.e. 50% does not come out on film/plate as 50%) gamma compensation allows you to correct this.

Please see the specific documentation on how to calibrate your device. It can be found on the Suite 12 DVD: "determine_gamma_english.htm"

7.7 PS/PDF marks

This tab offers you the possibility to have register marks added to the FlexRip output, when using the PostScript channel (AppleTalk, Hot Folder or Named Pipe). It includes a layout mode option for color strips and data legend, options for what should be shown and what shouldn't and an input field where you can enter your own text.

All this can be very important for quality control. E.g. the queue info can be added to the RIP output which will allow you to quickly check if the correct queue was used.



7.7.1 Layout mode

Select how you want your mark to appear: Horizontal, Thin Horizontal, Vertical, Thin Vertical and None. Starting point is the top left corner.

The default setting is *Horizontal*.

The height of the standard mark is 13 mm, a thin mark is 6 mm.

7.7.2 Include

7.7.2.1 Color strip

If you want to add a *color strip* to a film, plate or proof, specify what colors you want to include. Select: All colors or Only CMYK.

If you do not want to add a color strip, select (none).

7.7.2.2 Customer logo

Check the box if you want to add a *customer logo* to the proof.


Click the Browse button to open the 'Select a Customer logo file' dialog. Only .eps files can be used as a logo.

Note

Logo marks should be eps files in CMYK or 1 color. An RGB logo will have disappeared after ripping.

Warning

Take your logo mark into consideration when making plates for a one-color job. If your logo contains 4 colors, 4 plates will be created instead of the expected one.



7.7.2.3 Data legend

Check the boxes to indicate which items you want to include in the data legend. Use the text field to enter user-defined text.

Note

There are no requirements concerning the text layout. Be aware that template variables do not work for the data legend field.

7.8 Screening

This tab allows you to overrule screen parameters for each separation. The default option is (none). This means that the RIP will use the screen parameters specified in the job. Change these values only if you want to override the screen parameters specified in the job.


FlexRip offers an elaborate screening overrule mechanism to add more flexibility. It is possible to define spot colors and designer colors with LPI/angle/dot shape information. Moreover, the screening routines have been optimized to give more consistent output. E.g. dots with the same number of pixels will now have an identical shape (within the same dot shape).

Note

In case of PostScript input it serves both composite and separate PostScript. This screening menu should be seen as a filter after reading the input data and before the start of the actual ripping.

Warning

One can overrule screen parameters of all spot colors in the job, with the effect that all spot colors present in the job use the same screen parameters.



Select the color of which you want to change the settings in the list and apply the changes by selecting the correct Dot Shape, LPI or angle from the dropdown lists.

To define/add individual spot colors:

1. In the *Ink book*, select the book you want, or '(Unregistered inks)' if the spot color is not registered in your color database.
2. Enter the name of the spot color in the *Ink name* field.

What happens if you do not use these settings?

Then all rules previously mentioned are valid. The angle and ruling settings will be taken from the incoming PS/PDF file. In case of EskoLink input, the settings of the ticket will be taken.

What happens if you do use these settings?

If you select a Dot Shape and/or enter an angle and/or ruling value, the RIP will take these into account and will overrule all other incoming or requested values (overwriting the settings in the PostScript file or server ticket). This means that whatever you enter here will get the highest (overruling) priority!

Warning


Any Dot Shape entered in the Screening tab will overrule the Dot Shape selected in the Basic tab.

When should I use this menu?

When you do not control the incoming options:

- When you did not create the PS/PDF yourself and noticed that it contains ruling settings that are not supported by Esko screening rules.
- When you have a special workflow in which you want a special Dispatcher queue executing a fixed set of screening rules (contrary to a queue that listens to job-related settings).

7.9 Advanced options



7.9.1 Color conversion

Define how the RIP should handle undefined spot colors.

This has been deprecated, leaving only the No CMS option:

7.9.2 Use & Color management

This has been deprecated, as only the No CMS option is left.

7.9.3 Optimize separated postscript file processing

You can check this box if you think your separated PostScript file workflow is not efficient enough. You will win some time, but note that we do not guarantee PS or PDF marks to be printed correctly in all cases.

7.9.4 External search paths

1. Link external images (DCS, OPI...)

Enable or disable external linkage for DCS, OPI, etc images. This option is enabled by default.

2. Fail if file not found

When enabled, the RIP fails if external images are not found in the directory specified.


If the toggle is not enabled and a file is missing, the RIP will try to continue using PostScript data stored in the job.

3. Search paths

Specify RIP search paths for external images. Click *Add* to browse and add search paths. Click *Remove* to remove selected search path entry.

7.10 Debugging

This tool enables you to control the content of the log files. You can make your log files report basic info or you could have them report all kinds of details on the complete RIP action.



Why is this so interesting?

Extensive log files are very helpful when a problem occurs and you or our Customer Service is looking for an explanation and solution to the problem. Our advice is to always have extensive log files made. The actual log file can be consulted by double-clicking the process number in History View (first column 'job') or can be opened in WordPad or NotePad (standard text editors from Windows).

The log files (per Dispatcher) always reside in the Logging folder. Note that it is possible that the output folder has another name that you specified while configuring the FlexRip. The path listed below is the default path:

C:\Esko\bg_data_FlexRipapproval_v120\approval\Logging.

To change a debug setting, select the debug option and enter the new value in the input field. The minimum and maximum values are indicated.

Some advised settings:

- *Statistics*: advised setting: 5
- *Extra profiling*: advised setting: 1
- *Expose Ticket* (exptdebug): advised setting: 0
- *Statistics on error*: advised setting: 3. This will provide more info when errors occur.
- *Screening*: advised setting: 0

Warning

The higher the value, the more chance the system generates huge log files.

In the History View (page 80) chapter, you will find some guidelines on how to read log files and in the appendix there is a section that explains some classic errors (page 91).

Reset All: Will reset the debugging parameters to their default settings.

7.11 Copydot Tuning

7.11.1 Background

7.11.1.1 Performance & Memory Management

Lineart Pixel images are contourized in the FlexRip. This is the best solution for simple images (logos etc.) because, by contourizing, the images are handled as other linework. Transforming, clipping, trapping or screening of those images is done the same way linework is processed. This method however, gives problems for huge images containing extremely fine detail like screens. In such cases contourizing needs a lot of memory, which slows down the FlexRip. To overcome this problem, the FlexRip uses a copydot optimization.

7.11.1.2 Copydot workflow

Copydot images are bitmap images, representing pre-ripped or scanned pages. These images are stored in a bitmap file format (TIFF, DCS, EPS, ..). Most of the time we cannot see the difference with bitmap images representing logos or simple drawings. This makes it rather difficult for the RIP to decide if the bitmap should be contourized or not. In some cases, we can extract that information out of the job.

Copydots included in a DCS file are recognized as copydot. Copydots that are manually placed in the job by means of an editor are not recognized as copydot and by consequence, will be contourized.

7.11.1.3 Copydot and paint modes


A bitmap image can be set in 3 different modes:

1. ImageMask
Paint is only applied to black areas. White points are not part of the image. They always leave the background unaltered.
2. Image
Paint is applied to both black and white pixels.
3. Copydot
In paint mode masking, it behaves always as Image. For all other paint modes, the copydot image is bitwise stored into the background.


By default a bitmap image is set to 'ImageMask'. This means that when the paint mode is masking (e.g. opaque ink mode in Esko PackEdge), the bitmap image will always be contourized!

7.11.2 Queue Settings


To define or change the RIP copydot recognition, you must check the 'Include Tuning Options' box in the 'Input Queue Settings' of the Dispatcher ~~=Options~~
~~=Program Options~~ ~~=Input Queue Settings~~ ~~=Copydot Tuning Options~~.



This will give you four extra tabs in the Dispatcher, one of which is the 'Copydot Tuning' tab.



By default the 'Automatic Copydot recognition' is active.



The following 'rules' are used to treat an image as a copydot image:

- A copydot image must be a solid object. A screened bitmap image is never handled as copydot.

- A copydot image has a rather 'high resolution' and is not 'small'. A copydot image must have at least 1000 rows or columns.

7.11.2.1 Resample

When the RIP treats an image as a copydot image, the following happens:

1. With the size of the copydot image (inches, mm, ..) and the requested output resolution the number of resulting output pixels is calculated = X pixels.
2. The FlexRip checks the actual number of pixels that are in the copydot image itself = Y pixels.

If the difference between X and Y is higher than the value defined (default 1), then the copydot image will be re-sampled.

In case different copydots images in a job have slight differences in resolution, and you want to keep that resolution, you should set the resample value a bit higher (ex. 10).

Note


However, if the copydot image is set in a masking mode, then the image will again be contourized.

7.11.2.2 Abort

If the difference between X and Y is higher than the value defined, the RIP will be aborted. When set blank (also the default), the FlexRip will never be aborted.

8 Status Monitor

Start up the Status Monitor by selecting 'Status Monitor' from the Tools menu in the Dispatcher that you want to monitor. The Status Monitor gives information on the status of the current and past ripping processes.



8.1 General overview

In the Status Monitor three panes can be distinguished:

1. The *upper* pane presents all queues with their type and current status.
2. The *middle* pane displays **info** about the 3 RIP channels (2 Esko-native channels and one PostScript channel).
3. **Messages** are shown in the *lower* pane of the monitor.

The Rip kernel sends two types of information: messages and info.

Info data supersedes the previous data, such as the actual page number the RIP is processing. When ripping, the information "page number" starts with 1, becomes 2,

etc. When the RIP sends this kind of information, the Dispatcher knows that it can replace the previous value of "page number" with a new value.

Messages, however, are stored in a list by the Dispatcher. New messages are constantly added to the list. That is why you will see entries like 'processing job' when the job has long been processed already.

For each standard RIP process (or every time the RIP 'wakes up' after an internal error), you will see these 4 different messages (as seen also in above graphic of the Status Monitor window):

1. Identification (FRIP V12 + version date). The software version number and date of the Rip kernel.
2. Output identification (output module version number + version date). Shows the type of output module.
3. Input data channel (IOSTREAM): Reading the input (PS).
4. Processing job (path): Actually ripping, exposing, making output. All following jobs will only show the 'processing job' message.

8.2 Server menu

8.2.1 Connect to

This function allows the monitor to connect to a specific port number on a particular computer running a Dispatcher application. By default the Status Monitor connects to the Dispatcher that started up the application. If connection is to be established with another Dispatcher, possibly on another system, enter the host name and port number and click OK.

8.2.2 Trace messages

Trace information is info created by the Dispatcher each time an important event occurs (a job that is started...). It is used primarily for troubleshooting. Trace files are created by the Dispatcher and viewed in the Status Monitor. They are stored in the Logging folder.

Active: In the Dispatcher user interface it is possible to deactivate tracing. If tracing is not active then the option "Not Active" will be shown. Always leave tracing active. You will only need these trace files when Esko Customer Service asks you to consult or send one.


Note

Trace files can be viewed in text editors. The files contain hexadecimal characters, but WordPad has no problem showing them. You may, however, experience problems when opening trace files in other editors.

Note

If it is not possible to open a trace file, take a copy of the file and open this copy in a text editor.

9 History View




The screenshot shows a window titled "History View For Approval : HEKLA @ 5030 (Connected)". It has a menu bar with "Server" and "Help". Below the menu bar is a table with the following data:

Job Number	Job Name	Pages	Status	Input	For	Error Info	Logfile	Date Start	Time Start	Elapsed
3	Restart_PS_RIP		Success	Connection ...			Yes	19:06:2012	16:02:31	00:00:04
2	Product_Name		Warning	Hot Folder	Robert Ayers	PostScript error occurred	Yes	19:06:2012	16:02:23	00:00:02
1	Product_Name		Warning	Hot Folder	Robert Ayers	PostScript error occurred	Yes	19:06:2012	15:59:39	00:00:24


The History View program keeps track of processed jobs and enables you to consult their log files. The amount of messages in the History View is determined in the Program Options (Dispatcher → Options menu). The list can be emptied by choosing 'Clear History' from the Dispatcher Rip menu, which also deletes the actual log files. History View is a 'client' program of a Dispatcher. It will only show the history list when it is connected to a Dispatcher. When you start up History View, it will connect to the default port number of that Dispatcher (3031). In case you have multiple Dispatchers in your FlexRip configuration, History View will want to know to which Dispatcher it has to connect. Right-click the top window bar of the History View and choose Connect.

'Save As...' in the Server menu will save the currently selected log file.



History View For Approval : HEKLA @ 5030 (Connected)										
Server Help										
Job Number	Job Name	Pages	Status	Input	For	Error Info	Logfile	Date Start	Time Start	Elapsed
3	Restart_PS_RIP		Success	Connection ...			Yes	19:06:2012	16:02:31	00:00:04
2	Product_Name		Warning	Hot Folder	Robert Ayers	PostScript error occurred	Yes	19:06:2012	16:02:23	00:00:02
1	Product_Name		Warning	Hot Folder	Robert Ayers	PostScript error occurred	Yes	19:06:2012	15:59:39	00:00:24

Enter the correct Dispatcher port. The History View is now connected to that specific Dispatcher and will only show its specific history. You can now start up another History View and connect it to the other Dispatcher, etc...



Double-clicking the processed Job Number (left column) opens a view window of the log file that the RIP made of the entire processing of the PostScript file. The log files (per Dispatcher) always reside in the Logging folder. Note that it is possible that the output folder has another name that you specified while configuring the FlexRip. The path listed below is the default path.
E.g.: C:\Esko\bg_data_FlexRipapproval_v120\approval\Logging.

Note

Log files are text files so they can be viewed with standard Windows text editors like NotePad and WordPad. These offer search functionality, which is convenient when looking for specific info in these (possibly huge) log files.

```

JobNumber: 1  JobName: "Product_Name"

Total number of lines in file: 199  Logfile shown from line: 1

*** Localini file: D:\Esko\bg_data_flexripapproval_v120\Approval\tmp\localini_0.i
*****
[setup]
res= 2400
printername= KODAK_APPROVAL_XP
maximumheight= 33799
maxwidth= 52992
portid= 2345
pageclip= e
fripout= fripoutapproval
bps= 1
rd_b_pagecenter= 0
outdir= D:\Esko\bg_data_flexripapproval_v120\approval\Tmp
DeleteIp= 1
MediaSavingFlag= 2
RD_B_MAKECOMPOSITE= 1
frip_FailIfOPINotFound= 1
rd_opi= 0
rd_dcs= 0
rd_psimage= 0

```

The appendix of this document contains a more detailed explanation of possible errors that can be described in log files. The contents of the log file can be managed with the debug options in the Queue settings (see the Debugging (page 71) chapter). The next section will help you to read log files.

9.1 Log files: guidelines

When opening a log file, the *local INI* file is the first thing you see. But except for that, the log file is also extended with the *set of environment variables* that were used when ripping (those set up by the server, if any, and the ones specified in the FlexRip Configurator), and an indication of the *dispatcher queue* that was used to process the job. All this should make it easier for our Customer Service to determine the problem and for you to supply the required info to our Customer Service.

- **What dot / LPI / angle did the RIP really take?**

You will find this screening information by searching for these words:

'BG screen'

'Sampled Screen'

'lin'

In a PostScript workflow, the log file might first show some incorrect LPI and angle information, depending on the application and your debug settings (Typical are the offset settings of LPI 120 and angle 45). What you see here is the search order that the RIP is following. It starts with the default offset settings and then looks in the PostScript file to see what the

correct values are.

The RIP will take the requested PostScript file screening settings and the log file will show them. Use the following rule to check the correct dot, LPI and angle settings: the last time the screen info is mentioned just before the actual ripping starts ('start expose'). The screening settings shown there will be used to create the output file.

- When printing from Freehand, you can also search for 'Application' (and the next line will contain the really used screen settings).
'Sample Screen'
The first appearance is e.g. the fake default LPI of 120, but just continue to search. Usually, the third one already shows a change and you will see the actual 'lin' (lineature/ruling) taken by the RIP.
- **Output folder:** search for the word 'outdir'
- **Output name** (name of the output file): search for the word 'output' (at least in one of the expose ticket tables.)
- **Rip version:** search for following words:
I_CTRL_FI Identification (e.g. FRIP 12.0.0)
I_CTRL_OI Output Identification (e.g. TIFF MONO 12.0.02 (month day year))
The FRIP version is the version of the 'FlexRip kernel' (the base).
- **Font replacement:** search for the words:
'Not found', using (then you will find):
I_OSTREAM_BB Byte Buffer Dump
'fontname' not found, using Courier...
- **How many colors, separations, files were made?**
'start expose': Shows the time indication of each new file that is written.
'Progressline': Shows the actual ripping moment + progress info per inch.
'I_CTRL_PN' and 'page number': Shows the number of PostScript pages that the RIP is looking for.
Every log file will show this error at the end:
W_CTRL Warning: 'No data in output'
W_CTRL Warning: endpage (FALSE), page discarded
This simply means that there are no more separations described in that job, so immediately after this warning the RIP will end processing that file.

10 Workflow: flavors and hints

10.1 Who decides: the FlexRip or the operator?

You will have noticed that there are several ways to work with the FlexRip (See the Priority of Settings (page 42) chapter).

- Some people want the FlexRip to decide settings and even overrule the ones that the operator chose. This is often referred to as the 'fail-safe' method to avoid mistakes from operators.
- Some, however, do not want the FlexRip to take any decisions, but want it to keep all the settings the operator set in the PostScript file, or in the ticket in case of an Esko native workflow. This could be referred to as "All Power to the Operator" method.
- Settings that are not answered by the Dispatcher or ticket/PostScript file are taken from the Queue Defaults.

The decision is completely up to the customer. The difference between these choices is visualized by the use of the priority of RIP settings and the amount of Dispatcher queues. If queues take hard decisions, then their names better reflect what they do.

10.2 What is best: AppleTalk or Hot Folders?

As AppleTalk is no longer supported from Mac OS X 10.6 (Snow Leopard) onwards, Hot Folders is the remaining choice.

10.3 What if you rip for more than one output device?

If you have more than one output device that you want to send FlexRip output files to, you need more than one Dispatcher. Each Dispatcher is configured to serve one specific machine.

11 Screening on FlexRip

For complete and detailed info on Esko Screening, we refer to the screening documentation on the Suite 12 DVD.

In case of 'Precalculated' screening (native as well as PostScript input), the following should be considered:

The 'jump to' mechanism

The range of possible LPI's that the PPDs offer is a selection. The FlexRip will jump to the nearest LPI value that it has available. So if you ask 100 LPI and the RIP offers 94 and 104, you will get 104 LPI. Do remember that you cannot combine precalculated screening with DynaCell or PostScript screening. If you want another print angle or LPI than Esko offers, you can no longer combine it with an Esko dot shape.

Please refer to the Screening tab for more information on overruling.
See the ScreenFilter documentation on the Suite 12 DVD for information on how to swap PostScript screens with Esko screens.

12 Curve Pilot: Esko's Dot Gain Compensation tool

This section merely serves as an introduction. For more detailed information we refer to the Curve Pilot documentation on your Suite 12 DVD.

12.1 Terminology

- A DGC file stands for Dot Gain Compensation file. It is a curve.
- A Strategy (*.icpro) is a set of curves. One of the included curves will be chosen depending on specific a screen ruling, dot, angle or ink (separation).
- A SCRDC (Screen Based DGC) is a former set of curves. They can still be used; however, Curve Pilot 12 will not create SCRDC's anymore.

12.2 Basic explanation and general workflow

The high dot gain of e.g. the flexo printing process results in the need for compensation curves. With these curves, the imaged data are lighter, so the printed result is closer to the intended densities.

Esko prefers compensation curves to be executed in the RIP, since a fully digital workflow has many advantages:

- All data are print-process independent (same image for offset and flexo output).
- Digital tools can be trusted and are 100 % repeatable.
- Time gain.

A CtP (Computer to Plate) workflow will use different compensation curves than a CtF (Computer to Film). All the physical 'problems' with films and the 'film to plate' copy do no longer exist.

Example

The dot gain of digital flexo (CDI) approaches or even matches the Offset dot gain.

The main effect of the CtP workflow is the quality of the plate: dots are sharper (and stronger). This also results in very specific compensation curves.

Another reason for using curves is because of the nature of the printing process, but depends on your workflow.

If you work with '**independent**' data (i.e. your data are not, or only slightly, retouched for specific printing process reasons), then you will have to specify a flexo/offset compensation curve that will take care of the dot gain of the flexo/offset process. Again, this one may be general (DGC: one curve for all separations) or a specific one (Strategy: set of DGC's per dot/lpi/angle). These press curves will not be similar to curves that are used for conventional plates that were made through film contact! (Difference is less apparent for offset processes).

You also have a tool called '**target**'. In general, all curves can again be compensated with a 'target'. Adding these curves to (inside) an existing curve means: "Let's not forget that at image scanning time and while looking at monitors, we were already in an offset-Cromalin/WaterProof environment that was precompensated for offset". You might have the approval this flexo job based on an analogue Cromalin/WaterProof that shows offset dot-gain. If then you want the flexo print result to look like that Cromalin/WaterProof, you should deduct that offset gain from the one happening on the flexo press! That deduction is done by using that target (or reference) curve inside your flexo press dgc. What is then left over is the difference between flexo and offset dot gain.

Depending on the entire printing, the press compensation curves that are used to adapt the output files for a device will vary.

Advanced DGC requirements such as color based DGC strategies, are best handled in Curve Pilot (optional).

How do you make your DGC and ICPRO files?

Here's a short overview:

1. Output test jobs (strips) without any compensation curves.
2. Print on press in typical conditions.
3. Measure results (percentages / densities).
4. Fill in data in Curve Pilot.
5. Output test jobs again now with the compensation curves you made.
6. Print on press in typical conditions. The result should reflect the digital construction of the job.

12.3 Where are my SCR(DGC) files and Strategies?

Curve Pilot can be installed on the FlexRip or Automation Engine, but it is also possible to install it on other PCs.

If you have a server, all (scr)dgc files and Strategies will be located on the server. If you do not, they are stored locally on the FlexRip.

Make sure that:

1. the editors know where to find and write the curves.
2. the RIP (=Dispatchers) know where to find them.

On a new, non-customized FlexRip, the dgc files and Strategies are standard on
C:\Esko\bg_data_dgc_v010

The target curve(s) are in a subfolder 'refdgc':

C:\Esko\bg_data_dgc_v010\refdgc

More information on how to install the Curve Pilot, please refer to the Curve Pilot documentation on the Suite 12 DVD.

Tip

Always keep a backup copy of your curves, you do not want to loose all the work you put in there. Even a floppy disk could contain all your curves.

12.4 Using old DGC files

If you have DGC files from a FastLane v9.4 system or even older, you can continue using these DGC files on the FlexRip.

Best results are obtained after having loaded and saved the DGC files into Curve Pilot. This will improve the quality and smoothness of the curve. We refer to the appendices in the Curve Pilot manual on the Suite 12 DVD for more elaborate information.

13 Data backup and customization

A working FlexRip contains the standard FlexRip software that was configured to the customer's specific devices and workflow (Dispatcher Queues: their type, amount, names and their settings). This configuration results in small files that are very typical per customer. Configuration files are backed up by the FlexRip Configurator. Please refer to the Configurator documentation for more information on backing up configuration files.

The FlexRip contains output files. We see that some customers back up their output files and some do not. This depends very much on other archiving methods in the workflow. How you back up all these data is your decision. Your system manager should advise the workflow responsible what devices and procedures are available with this Windows2003 computer. You could copy data to another disk to avoid loss in case of hard disk problems. You could share a part of the FlexRip hard disks and copy the data to another computer that has a CD writer (or optical disks or...). Some more advice though:

Back up your DGC data

Copy your DGC files to the backup folder you made on your data disk or copy them all to an external disk. Do this regularly.

Warning

Never put a (any kind of) file that was on a CD or a DVD on a FlexRip Hot Folder. A file that comes from a CD or DVD-ROM is R.O.: Read Only! This means that after ripping the file, the RIP will not be able to delete the file and will rip it over and over again until the hard disk where your output folder is situated, is completely filled up.

14 Classic errors and their explanation

The History View program will show if a RIP action was completed successfully or if it encountered an error. Error Info usually concerns 'Internal Errors' or 'PostScript Errors'. As said before, a warning in a FlexRip log file is not always an error, but still it will appear in the log file.

For instance, in some log files, you will see the following warning a number of times:

W_DATA Warning: Output resolution not integer...

This is completely normal. Since the effective PPI has to be an 'integer' number, the RIP will change your resolution in background just a little bit, e.g. from 2104.9 to 2105 ppi.

Another warning that appears in every log file (at the end) is

W_CTRL Warning: No data in output!

W_CTRL Warning: endpage(FALSE), page discarded

I_TCTGEN_INFO no Contone data Processed.

This all means that the PostScript Interpreter is looking for the next color ('page') but does not find any. It indicates that there are no more separations described in the PostScript file and that all pages (=inks =separations) have been ripped.

You should in fact only be alarmed if you do not see the word 'Success' in the Status column of the History View.

- **PostScript errors** are encountered by the FlexRip's PostScript Interpreter. This could be e.g. because the PostScript file is not complete, because it contains inappropriate PostScript commands for the FlexRip ("dirty PostScript"), or because the FlexRip does not understand the commands.
- **Internal errors** have to do with the general working of the FlexRip or with the status of the RIP itself. If someone, during a RIP action, closes the Dispatcher or chooses the 'Abort job' function, you are bound to get this kind of error. You will also get an internal error if the RIP is asked to do things it cannot do. An example: the PostScript file might be read without problems, but it asks the RIP to execute a DGC curve that does not exist or to output the e.g. LEN or TIFF file to a folder that was deleted. Both of these operator mistakes will cause internal errors.

Warning

Double-clicking the job number in the History View will show you the log file in an internal window. You may find it much more practical to read large log files when you open them in a simple standard text editor (with a search function!) that Windows offers like 'NotePad' or 'WordPad'.

What follows is a list of some typical errors and the way they are described in the log file. An error is always first described with a code, followed by some more or less 'readable' explanation.

Example

Example of such a code: 'E_DGCNAM_IE':

E = Error (I = Info; W = Warning)

DGCNAM = something wrong with the name of the dgc file

IE = It is an Internal Error

These codes are very valuable for our Customer Service, so do mention them too when reporting problems.

14.1 Classic PostScript errors

14.1.1 Examples

- **General warning**

E_CONTROL_PE PostScript error occurred (parser warning: PS error happened)

This is a standard line for most PostScript errors, and will be preceded or followed by a more specific message.

- **Rip was stopped during reading of the PostScript file**

W_CTRL Warning: FastRip cancelled

This indicates that something interrupted the RIP. It was suddenly stopped and the PostScript file could not be read anymore.

To check: Did someone choose 'Abort Job' from the Dispatcher's Server menu? Did someone close the Dispatcher program or even shut down the FlexRip?

See to it that the RIP is started and just try to send the job again. It is possible that you do not have to restart the Dispatcher, because the RIP normally restarts automatically when any Queue or Hot Folder receives a new PostScript file.

- **'Illegal' dot types in PostScript**

If you input from ArtPro, you might find following error in the log file and similar 'Error Info' in the History View:

I_OSTREAM_PEMSG %%%[Error: rangecheck: Offending Command: set halftone;ErrorInfo: Halftonetype 95]%%%

In ArtPro it is possible to select a non-standard dot (in the 'Separations' menu). These dot types for a Nexus RIP should not be allowed in PostScript code that is not made for such a RIP. Please see the Printing documentation (chapter 'Remark on printing from ArtPro').

Solution: Overruling the dot in the Dispatcher's Queue settings does not help. As said before, the job has to be printed again from ArtPro and a standard PostScript dot (top part of list) or no dot has to be selected in the menu 'separations'. Then the PostScript file will be fully readable and the RIP will continue to see what Esko dot has to be used in the end.

Using ScreenFilter is another option. If multiple dots are defined in ArtPro you will need the ScreenFilter to handle these jobs. ScreenFilter will capture the screening info and will allow you to define swap tables for incoming screens.

For more information, please refer to the ScreenFilter documentation on the Suite 12 DVD. There's even a third solution to overcome this problem. You can rewrite the PostScript file in ArtPro using PS screening instead of Nexus screening. The PS screening of ArtPro will work if you switch to "PostScript screening" in the FlexRip Dispatcher. All dots as described in the PS file will then be correctly output.

- **Ink name descriptions**

W_CLASS Warning: Multiple invocations of PLATECOLOR on this

Page

Meaning: Output file names always get a suffix based on the ink name description in the PostScript file. This official description of the separation name is the command 'PlateColor'. If the RIP finds (in 1 page, so within the same separation) multiple descriptions of this ink, it will give this warning. The warning indicates that this behavior is not standard, but does not have to be a problem.

- **Font not available**

When a font is not included in the PostScript file, and not available in the RIP itself, the following error messages will be displayed:

I_OSTREAM_BB Byte Buffer Dump (length: 46 bytes)

TextileRegular not found, using FontNotFound..

I_OSTREAM_BB Byte Buffer Dump (length: 55 bytes)

%%[Error: invalidfont; OffendingCommand: findfont]%%.

I_CONTROL_INFO Parser info: %%%[Error: invalidfont; OffendingCommand: findfont]%% I_OSTREAM_BB Byte Buffer Dump (length: 63 bytes)

%%[Flushing: rest of job (to end-of-file) will be ignored]%%.

I_CONTROL_INFO Parser info: %%%[Flushing: rest of job (to end-of-file) will be ignored]%%

E_CONTROL_PE PostScript error occurred (Parser warning: PS error happened)

14.1.2 Problem solving: 'capture' the PS file

If there is some mysterious problem with reading a PostScript file, and all other obvious rules have been checked, then our Customer Service may ask you to provide us the 'Captured PostScript file'. This is a text file that includes the PostScript file itself plus a lot of other relevant data. So a 'captured PostScript file' is not just the PostScript file that was intercepted, it is more than that.

How to 'capture' a problem file?

1. Try to reproduce the problem with a small PS file (less data? only one separation?)
2. Wait until all Dispatcher queues are in idle status.
3. Enable the 'Capture PostScript file' in the Program Options of the Options menu in the Dispatcher and confirm with OK.
4. Have the problematic Postscript file ripped again and wait until the error shows up again. This time the PostScript file was also 'captured' in a temp folder.
5. The captured Postscript file will be called ps_trace_1.txt and can be found in the Tmp folder. Note that it is possible that the output folder has another name that you specified while configuring the FlexRip. The path listed below is the default path.
C:\Esko\bg_data_FlexRipapproval_v120\approval\Tmp
Now deliver this .txt file to our Customer Service.
6. Do not forget to switch off the 'capturing' afterwards! So disable the 'Capture PostScript file' in the Program Options of the Options menu in the Dispatcher and confirm with OK.

14.2 Classic internal errors

- **Screen not found**

E_SCRSEL_IE Internal error (Screen file xxx not found...)

Meaning: The screen file (.isb or .csb file) you requested was not found. A screen file is an area of dots of 1 type, 1 angle, 1 size (lpi) and 1 resolution (ppi).

Example

the screen file f8205c.isb represents:

*f: flexo angles
82: angle 82
05: number of resolution set of that type
c: circular dot*

Check if that dot is available on your FlexRip. If it is not purchased, it will not

be in the central folder for the 'screen files':

C:\Esko\bg_data_screens_v010

Is the angle you requested a flexo angle? If not, the RIP will look for an Offset

screen file and those have a name starting with an 'o'.

- **(Scr)dgc files not found**

E_SCRSEL_IE indicates that the RIP has trouble reading the DGC file.

```

JobNumber: 16  JobName: "Unknown"

Total number of lines in file: 156      Logfile shown from line: 137

I_JOBCTRL_JN      Job name (d:\esko-graphics\bg_data_flexripdcs_v012\unscreened\
tmp\localini_0.ini)
I_CB_INFO         Extension identification: Antialias V5.1.02 (Nov 22 2003)
I_CB_INFO         FRip/IPL: Extension identification: INKPLANNER V2.0.01 (Nov 22
2003)
I_CB_INFO         Extension identification: FRIPUTUTIL V5.2.38 (Nov 22 2003)
I_CB_INFO         Extension identification: DCS V5.2.01 (Nov 22 2003)
I_CTRL_OI        Output identification (EPS V5.2.02 (Nov 22 2003))
I_DEF_INFO        Using default INI file d:\esko-graphics\bg_data_flexripdcs_v01
2\unscreened\data\default_out_dcs.ini!
I_SCRSEL_INFO     ICPro Ccurve library returned error with type 2 message : Coul
d not open "\\proof\bg_data_dgc_v010\40w0.dgc" for reading
I_SCRSEL_INFO     ICPro Ccurve library returned error with type 2 message : Coul
d not load bytestream of file "40w0.dgc"
I_SCRSEL_INFO     ICPro Ccurve library returned error with type 2 message : Coul
d not initialize curve resource "40w0.dgc"
E_SCRSEL_IE       Internal error (DGC file read problem (File .\fripctrlsel.c lin
e 602 dd Nov 22 2003))
DEBUG : Number of objects in the process link factory : 90
DEDUG : Number of objects in the process factory : 45
    
```

This means that the FlexRip is not able to read the (scr)dgc file specified, because:

- the share could not be reached.
- the file is not present.
- the file is corrupt.

Perform the necessary checks to verify if the DGC file is present and opens correctly.

- **Problems with writing the actual output file**

E_CB_IE Cannot create output file(s) ...

E_CTRL_CCF Cannot create file (fripout(5): *E_openfile*)

Meaning: The RIP would like to, but just cannot create a plate file or the

original output file. The output directory will be created when necessary. Check the Queue settings to see where the RIP wants to write that output file.

Or in case of:

E_DEVCOM Output Device communication Error

Check if the hard disk (the one where the output folder is) still has space left to write the output file? The hard disk may be filling up. If so, clean up and delete some files or re-direct the output to a folder on another disk.

15 General troubleshooting

15.1 Queue settings 'disappear'

My Dispatcher Queue Settings seem to disappear...

Although this is not known as a bug in the FlexRip software, we would like to comment on that. If you notice that queue settings get 'lost', then this is not a problem in the FlexRip software itself, but in what surrounds this software. So please look for the problem in the 'environment'.

When you click OK after checking or changing Dispatcher Queue Settings, a small .usr file is adapted. This .usr file (as all your specific settings of your Dispatcher) is in: C:\Esko\bg_data_FlexRipapproval_v120\approval\Data


The date and time of these files indicate when the Queue settings have been changed. When that C drive is full, the RIP will have problems accessing and writing those .usr files. So do check if your system drive is full and certainly why it was full. Make sure that all your Hot Folders (large incoming PostScript files) or output folders (where the CT files are written) are on your Data drive. Also check whether or not your Hot Folders (Queue Info) delete the PostScript data after ripping. Make sure that they do.

15.2 My input queue shows a 'fail' status

The AppleTalk queue is not automatically put in the 'idle' status.

If an item is not working because certain elements are not installed, the Dispatcher will go into a "fail" status.

In this case the AppleTalk services are not running. Activate the AppleTalk services and open the Dispatcher again.



15.3 The system disk is filling up

Why is my C drive so full?

If your C drive is filling up and you have no idea why, then check the contents of the Tmp subdirectory of the data tree of the FlexRip flavor. If you see files with strange names like 'stream_cdlclass57628_6234' (always begins with stream_cdlclass, then one or two numbers and no extension), then these may be remains of a PDF file that has not been ripped successfully. Before ripping a PDF file, it is first converted to PostScript. The temporary PostScript files that are generated are stored in the bg_tmp directory and will be deleted after ripping. However, if the RIP ends with an internal error during ripping (crash, read only PDF file from a CD...), it will stop but it will NOT delete these temporary files. In this case, you'd better delete them yourself. Keep at least one to show at Esko Customer Service.

15.4 FlexRip rips my file over and over again

I can't stop the RIP from ripping a certain job over and over again.

This is what happens when you have put a read-only file on a Hot Folder. The RIP will try to delete it after the ripping but it can't, since this requires writing permission. Solve this by stopping the Dispatcher (so 'abort job' is not enough!),

deleting the read-only file, and deleting all the unnecessary output files it created.
Restart the Dispatcher.

16 Frequently Asked Questions

16.1 FlexRip software version

What version of FlexRip software do I have?

The software version can be found in every log file. You'll first see the ini file, then the environment variables and below that, the software version will be mentioned.

16.2 Extra software on the FlexRip

Can I install some extra software on my FlexRip?

No, unless approved by Esko. Whenever you add, remove or reconfigure of software on your FlexRip should be requested and reported to Esko Customer Service. In general, upgrading any of the software that is already installed (Windows, modem software, DiskShare) has to be reported and requested. Installing additional new software will probably be forbidden. Any request will be considered though. Send this request to the Customer Service department.

16.3 Screensaver

Can I use a screensaver on my FlexRip?

No! Even screensavers use CPU activity and all CPU on a FlexRip should be dedicated the RIP itself. When a FlexRip is well configured, it should be quietly doing its RIP work all day. Nobody should change any Queue settings or monitor or read log files. This means it would even be logical to switch the monitor off.

16.4 Windows version

What version of Windows do I have?

In Explorer, choose 'About Windows' from the 'Help' menu and you will get an exact description of your version of Windows on the second line.



16.5 Rebooting the FlexRip

Should I reboot the FlexRip occasionally?

Yes. We have experienced that this WindowsNT-driven computer likes a 'shower' every week. It will free up some hanging memory and therefore be a little faster afterwards. Please do this occasionally, even when you would not even notice any loss of speed.

16.6 FlexRip's computer name

What is the name of my FlexRip?

If in doubt: open a command prompt window (Start → Programs → Command Prompt) and type: set computername. This will show the actual computer name and more network information. This name is set by Esko. Do not change it. When still desired, contact Esko first.

16.7 Info on the network address

TCP/IP info:

Frequently Asked Questions

If in doubt: open a command prompt window (Start ⇒ Programs ⇒ Command Prompt) and type *ipconfig/all*. This will list all necessary info on the TCP/IP configuration of this machine.


17 Appendix

17.1 Connection to DTP stations


17.1.1 How to share FlexRip volumes for a Macintosh (Microsoft Windows 2000 or 2003 Server)

Windows 2000 Server


1. Right click "My Computer" and select "Manage".




2. Go to “Shared Folders” =Shares and select “New File Share...”



3. Select the folder or drive and fill in the share name. Do not forget to take the naming policy into account.



4. The next dialog allows you to set the permissions. Keep the default selection (All users have full control).




Windows 2003 Server


1. Right click "My Computer" and select "Manage".




2. Go to “Shared Folders” =Shares and select “New File Share...”



3. Browse to the folder you want to use as a share.



4. Define the share settings.



The screenshot shows the 'Share a Folder Wizard' window, specifically the 'Name, Description, and Settings' step. The window has a title bar with the text 'Share a Folder Wizard' and a close button. Below the title bar is a header area with the title 'Name, Description, and Settings' and a sub-instruction 'Specify how people see and use this share over the network.' To the right of the header is a small icon of a folder with a hand. The main area contains instructions: 'Type information about the share for users. To modify how people use the content while offline, click Change.' Below this are two sections for user permissions. The first section is for 'Microsoft Windows users' and is checked. It contains four input fields: 'Share name' (containing 'customersAE'), 'Share path' (containing '\\RDALPHA07\customersAE'), 'Description' (empty), and 'Offline setting' (containing 'Selected files and programs available offline' with a 'Change...' button next to it). The second section is for 'Apple Macintosh users' and is also checked. It contains one input field: 'Share name' (containing 'customersAE'). At the bottom of the window are three buttons: '< Back', 'Next >', and 'Cancel'.

Share a Folder Wizard

Name, Description, and Settings
Specify how people see and use this share over the network.

Type information about the share for users. To modify how people use the content while offline, click Change.

☒ Microsoft Windows users

Share name: customersAE

Share path: \\RDALPHA07\customersAE

Description:


Offline setting: Selected files and programs available offline [Change...](#)

☒ Apple Macintosh users

Share name: customersAE

< Back Next > Cancel

5. Set the permissions and click Finish.



The screenshot shows the 'Share a Folder Wizard' window, specifically the 'Permissions' step. The window has a title bar with the text 'Share a Folder Wizard' and a close button. Below the title bar is a header area with the title 'Permissions' and a sub-instruction 'Specify permissions for the share.' To the right of the header is a small icon of a folder with a hand. The main area contains instructions: 'Use one of the following basic share permissions or create custom share and folder permissions.' Below this are four radio button options: 'All users have read-only access', 'Administrators have full access; other users have read-only access', 'Administrators have full access; other users have read and write access' (which is selected), and 'Use custom share and folder permissions' (with a 'Customize...' button next to it). Below the radio buttons is a paragraph: 'Permissions you set on this page only control access to the share; you might also want to set permissions on individual files and folders. For more information about permissions, see [Help](#).' Below this is another paragraph: 'To create the share, click Finish.' At the bottom of the window are three buttons: '< Back', 'Finish', and 'Cancel'.

Share a Folder Wizard

Permissions
Specify permissions for the share.

Use one of the following basic share permissions or create custom share and folder permissions.

☐ All users have read-only access

☐ Administrators have full access; other users have read-only access

☒ Administrators have full access; other users have read and write access


☐ Use custom share and folder permissions [Customize...](#)

Permissions you set on this page only control access to the share; you might also want to set permissions on individual files and folders. For more information about permissions, see [Help](#).


To create the share, click Finish.

< Back Finish Cancel


6. In the Computer Management dialog, right click “Shared Folder” and select “Configure File Server for Macintosh...”




7. Choose “Apple Clear Text or Microsoft”.



8. In the Computer Management dialog, go to “Shares” and select the correct share.



9. Change the properties for that share. By default “Read only” is activated.



17.1.2 How to share FlexRip volumes for a PC (Microsoft Windows 2000 Server)

Before being able to share, two conditions have to be met:

1. The FlexRip folder has to be 'shared' open enough for the user who wants to access it (so there are no problems with file permissions).
2. The user on the DTP PC has to be known on the FlexRip or has to be able to log in as user 'Guest'.

Therefore:

- On the FlexRip: share the volume and open its permissions:
 1. Right click the folder that you want to be visible for other PC's.
 2. Choose 'Share this folder...'.
 3. Activate 'Shared as:' and keep the proposed name (e.g. 'Hot Folders').
 4. Keep the user limit to 'Maximum Allowed'.
 5. Click 'Permissions': Set 'Full Control' for 'Everyone'.
 6. Click OK and click OK again in the 'Folder properties' window.

- On the FlexRip: enable the account of user 'Guest':
 1. Start ⇒Programs ⇒Administrative tools - Computer Management.
 2. You will see 3 users: Administrator / Guest / Iusr_nameofrip
 3. Double click the user 'Guest' to open its window 'Guest properties'.
 4. De-activate 'account is disabled' (= so do enable this account).
 5. Click OK.
 6. Close the Computer Management dialog (top-right X). No restart is needed.

17.1.3 How to share FlexRip volumes for a Macintosh or a PC (Microsoft Windows 2000)

Note

Following will not be possible when your FlexRip does not have the required version of Windows: Microsoft Windows2000 Server.

Note

Folders can be shared for Microsoft Windows AND Apple Macintosh at the same time. Therefore, the procedure for both will be explained together.

The FlexRip folder has to be 'shared' open enough for the user who wants to access it (so there are no problems with file permissions). The user on the DTP PC or Mac has to be known on the FlexRip or has to be able to log in as user 'Guest'.

Therefore:

1. Log on a user 'Administrator'.
2. Start ⇒Programs ⇒Administrative Tools (Common) ⇒Computer Management.
3. Have the right computer selected ("local" or name of your FlexRip). If not visible, try to select the exact domain or ask your network manager for more information.
4. System Tools ⇒Shared Folders ⇒Shares. You will see that a default volume is already mounted (C:\Microsoft UAM volume).
5. Select "Shares".
6. Choose Action ⇒New File Share. Enable "Microsoft Windows" if you want a Windows share, enable "Apple Macintosh" if you want a Macintosh share. Enable both if you want a Windows AND Macintosh share.
Set the following options:
Computer: name of the FlexRip
Folder to Share: enter the correct Hot Folder path
Share Name: Windows Share Name
Share description: brief description of the share (optional)
Macintosh share name: The volume name is what will pop up in the Macintosh Chooser application and will then be set visible on the Macintosh Desktop.
7. Click "Next".

8. Enable "All users have full control".
9. Click "Finish".

Note

Above procedures use the standard 'Services for Macintosh' that Windows2000 offers. Customers who would like to improve the file transfer speed between Macintoshes and the FlexRip (Windows2000), could consider having this connection via a software product of CYAN Software GmbH called 'MacServerIP'. We successfully tested this in a FlexRip workflow and have noticed file-transfer speeds of average 3 times faster (compared to the standard Windows services). As this is only advice, we refer for all further info (and responsibility) to this company's web site: www.cyansoftware.com.

17.1.4 How to mount FlexRip volumes on a PC (Microsoft Windows 2000)

Mounting FlexRip Volumes on a PC will be done by simple 'mapping of network drives'. We will explain this with an example.

The DTP PC will map a drive 'X' to represent the folder 'Hot Folders' on the FlexRip. This way, the PC operator can easily print-save the PostScript files directly on the Hot Folders.


On the DTP PC: map a network drive to the shared FlexRip folder.

1. Start ⇒Programs ⇒Accessories ⇒Windows Explorer.
2. In Explorer: Tools ⇒Map network drive.
3. Choose a free drive and type the correct path to the FlexRip folder:
E.g. X:\ \fripnt01\hotfolders
Activate 'reconnect at logon'.
4. Click 'OK'.
5. The mapped drive should now appear in the Windows Explorer. Should you experience problems, ask your (Windows) system manager to do this for you.

Note

Mapping a network drive will not ask you for a password because you enabled the guest account on the FlexRip. If you write a PostScript file on a FlexRip's Hot Folder, the PostScript file will initially have owner 'Guest', but after being ripped the resulting output file will have owner 'Administrator' (like it should be).

17.1.5 How to mount FlexRip volumes on a Macintosh OS9 or older

1. Click  Chooser.
2. In the Chooser dialog, select the AppleShare icon and choose the appropriate share from the list.
3. Enter the correct password if asked for.
4. Click Connect.

The selected share will appear on the desktop.

17.1.6 How to mount FlexRip volumes on a Macintosh OSX or later

1. In Finder, select Go ⇨ Connect to Server.
2. Select the server and the correct share from the list.
3. Enter the correct password if asked for.
4. Click Connect.

The selected share will appear on the desktop.

17.2 Merging

It is not possible to merge files on the FlexRip. Merging can be done via the ticket in Automation Engine or the FlexRip Pilot.

For more information on merging, we refer to the Automation Engine documentation.

17.3 What about OPI?

A FlexRip is by no means an OPI server itself (so not a 'provider'): a FlexRip should therefore always receive 'fat' PostScript data. These data may have passed an OPI server (where the missing or low-resolution images were replaced with high-resolution images). In that case, the DTP operator prints to the OPI server, which (after doing its OPI replacements) transfers (spools) the now 'fat' PostScript further

on to a specific, print queue on to the FlexRip.

Note

Automatic replacement of low-resolution images by high-resolution images of course enhances the workflow. If you like OPI to be done before the PostScript data go to the FlexRip, you may do this. But as OPI links are not mentioned in the product specification of a FlexRip, Esko is not the responsible for its connectivity. All info on how to connect the OPI server's output channel to the FlexRip's input channels should be available to Esko via the FlexRip pre-installation question list. The setup of this OPI workflow can then be established during the initial installation training by the Esko instructor, this only by joining forces between the 2 parties: the FlexRip instructor and the customer's in-house specialist in that OPI software.

18 Glossary

C

CCITT Compresses data using algorithm (the CCITT encoding is specialized to 1 bit per pixel. a bit-oriented encoding facsimile standard). This monochrome image data at 1 bit per pixel

D

DynaCell screens Esko DynaCell screens don't have the limitation of a limited set of available rulings and angles. This is reached through on-the-fly calculation of the screening pattern. The screens are calculated during the RIP process based on the precise ruling, angle and dot shape definition. Since this process happens in the RIP black box just before exposure, the result of this calculation has never been watched or optimized by an Esko engineer. As a result, these screens have a lower quality than the pre-calculated screens.

E

Esko Classic (precalculated) screens Pre-calculated means that the aspect, the form, the rulings and the angles of the screen are pre-defined in the Esko screening labs. These screens are the result of advanced engineering work. The screens are optimized for a smooth aspect, good behavior on the different printing processes, lack of artifacts etc. Furthermore, the screens are designed following a system of screen angles that avoids moiré between the main colors (cyan, magenta and black). The use of pre-calculated screens allows to support advanced screening features like stochastic screening (Monet Screens) and transitional screening (SambaFlex Screens). Pre-calculated screens have only one disadvantage: since these screens have been designed and tested one by one, there is only a limited number of precalculated screens. Although the total number exceeds 2000 different screen ruling/angle/dot shape

combinations, it is very well possible that no precalculated screen is close enough to a customer's wish. This happens specifically when other angles than flexo or offset angles are demanded. Esko pre-calculated screens with conventional screen patterns are called Esko Classic screens.

F

Flate The lossless deflate compression algorithm is based on two other compression algorithms: Huffman encoding and LZ77 compression. Deflate is a smart algorithm that adapts the way it compresses data to the actual data themselves.

J

JPEG This file format for color-rich images was developed by the Joint Photographic Experts Group committee. JPEG compresses graphics of photographic color depth better than competing file formats like GIF, and it retains a high degree of color fidelity. This makes JPEG files smaller. You can choose how much to compress a JPEG file, but since it is a lossy format, the smaller you compress the file, the more color information will be lost.

- JPEG limited compression: very acceptable data loss
- JPEG low compression: very acceptable loss of data
- JPEG standard low compression:
- JPEG standard compression
- JPEG standard high compression
- JPEG high compression
- JPEG extreme compression: heavy compression, lots of data is lost.

L

LEN A LEN file is a bitmap file that is made by a FlexRip/C. 'LEN' stands for 'run Length ENcoding', which is a way of encoding bitmap files. The only information in this kind of file is where to put dots and where not. The Grapholas software will then expose these dots on the printing plate on the CDI drum.

The LEN file itself can not "remember" any ink information of the separation. That's why the user will have to specify which ink the LEN file is representing (unless he wants a Black & White proof of course). LEN files have high resolutions as 2100 ppi and more. Proofing on an HP proofer is typically done at a lower resolution like 600ppi.

LZW Compresses data using the LZW (Lempel-Ziv-Welch) adaptive compression method, optionally after pretransformation by a predictor function. This is a good general-purpose encoding that is especially well suited for natural-language and PostScript-language text, but it is also useful for image data.

P

PostScript screening

Using PostScript screening implies that all the information needed to build up the dots has to be in the PostScript file. There is no such thing as a combination of PostScript and Esko screening! In every DTP application, you can choose the LPI from the Esko PPD or you can overrule it. Also the print angle will be offered by the PPD but the DTP applications permit you to enter other angles. If you send these data to the RIP, the 'Esko screening' setting will again change these values via its own 'jump-to' mechanism. This means that the RIP will automatically jump to the nearest LPI or angle that is supported. If you do not use 'Esko screening' but 'PostScript screening', these 'special requests' will indeed be realized by the FlexRip.

If you activate PostScript screening, the dot shape should also be described in the PostScript file. If you cannot select dot shapes in your DTP application, then it will probably describe the standard Fogra Round dot shape (see also Esko's Fogra Round).

Precalculated screens (Esko Classic) See Esko Classic (precalculated) screens.

R

RLE RLE stands for Run Length Encoding. It is a lossless algorithm that only offers decent compression ratios in specific types of data.

RLE is one of the easiest compression algorithms there is. It replaces sequences of the same data values within a file by a count number and a single value.

RLE compression can be used in the following file formats: * TIFF files and * PDF files.

INDEX

A

- Abort (copydot), 76
- Abort Job, 26
- About Dispatcher, 32
- Advanced options (Queue settings), 69
- AppleTalk or Hot Folders, 85

B

- Backup, 90
- Basic tab (Queue settings), 43
- Basics, 13

C

- Calibrated color spaces, 59
- Calibration, 63
- Capture PS file, 29
- Clear History, 25
- Color conversion, 69
- Color strip, 65
- Configuration set, 51
- Connect to, 78
- Connected monitors, 32
- Connection to DTP stations, 103
- Copydot Tuning (Queue Settings), 72
- Customer logo, 65
- Customization, 90

D

- Data backup, 90
- Data legend, 66
- Debugging (Queue settings), 71
- Device type, 44
- Dispatcher, 24
- Dot Shape, 45

E

- FlexRip queue, 18
- Esko Curve Pilot, 87
- Exit Dispatcher, 27
- External search paths, 70

F

Fail status, 97
FAQs, 100
File format, 15

H

Hints, 85
History, 28
History View, 31, 80

I

Images with scaled resolution, 59
Imaging options, 45
Info menu, 31
Input queue settings, 29
Input queues, 32
Curve Pilot (Queue settings), 61
Internal errors, 94

L

Laydown options, 47
Laydown order, 47
Layout mode, 64
Log files, 83
LZW, 117

M

Media saving, 52
Merging, 113
More than one output device, 85
Mount FlexRip volumes on PC, 112

N

Native input (Queue settings), 59
Native workflow, 14

O

OPI, 113
Optimization, 57
Options menu, 27
Output file name, 51
Output module, 44
Output tab (Queue settings), 50

P

- Page size, 44
- PDF password , 58
- Performance (Queue settings), 30
- Ports, 32
- PostScript errors, 92
- PostScript options, 55
- PostScript workflow, 13
- Press dot gain compensation, 63
- Priority of settings, 42
- Program options, 27
- PS color management, 58
- PS/PDF Input (Queue settings), 54
- PS/PDF Marks (Queue settings), 63
- Pure black overprint, 57

Q

- Quark trapping, 58
- Queue defaults, 29
- Queue settings, 42
- Queue types, 32

R

- Reboot the FlexRip, 21
- Resample, 76
- Resolution, 45
- Restart PS rip, 27
- Restricted file names, 51
- Rip menu, 25
- RIP priority, 30
- Rotation, 44

S

- Scale, 44
- Screen swap table, 57
- Screen type, 55
- Screening, 86
- Send jobs, 25
- Server menu (Status Monitor), 78
- Share FlexRip volumes for Macintosh, 103
- Share FlexRip volumes for PC, 110
- Shutting down the computer, 21
- Shutting down the Rip, 20
- Software version, 100

Starting up the computer, 19
Starting up the Rip, 20
Status Monitor, 31, 77

T

Template examples, Error: Reference source not found
Template variables, Error: Reference source not found
Tools menu, 31
Trace messages, 28, 79
Troubleshooting, 97

W

Workflow, 11
Workflow description, 16